

Effect of Thomas Rotation on the Lorentz Transformation of Electromagnetic fields

L. Malhotra,¹ R. Golub,² E. Kraegleloh,³ N. Nouri,^{1,*} and B. Plaster¹

¹*Department of Physics and Astronomy, University of Kentucky, Lexington, Kentucky 40506, USA*

²*Department of Physics, North Carolina State University, Raleigh, North Carolina 27695, USA*

³*Department of Physics, University of Michigan, Ann Arbor, Michigan 48109, USA*

A relativistic particle undergoing successive boosts which are non collinear will experience a rotation of its coordinate axes with respect to the boosted frame. This rotation of coordinate axes is caused by a relativistic phenomenon called Thomas Rotation. We assess the importance of Thomas rotation in the calculation of physical quantities like electromagnetic fields in the relativistic regime. We calculate the electromagnetic field tensor for general three dimensional successive boosts in the particle's rest frame as well as the laboratory frame. We then compare the electromagnetic field tensors obtained by a direct boost $\vec{\beta} + \delta\vec{\beta}$ and successive boosts $\vec{\beta}$ and $\Delta\vec{\beta}$ and check their consistency with Thomas rotation. This framework might be important to situations such as the calculation of frequency shifts for relativistic spin-1/2 particles undergoing Larmor precession in electromagnetic fields with small field non-uniformities.

I. INTRODUCTION

As pointed out by Thomas [1], two successive non collinear Lorentz boosts are not equal to a direct boost but to a direct boost followed by a rotation of the coordinate axes. That is,




FIG. 1. Schematic of the boosts. $\vec{\beta} + \delta\vec{\beta}$: Direct boost, $\vec{\beta}$: First successive boost, $\delta\vec{\beta}$: Second successive boost in lab frame, $\Delta\vec{\beta}$: Second successive boost with respect to the inertial frame with boost $\vec{\beta}$.

$$\begin{aligned} A(\vec{\beta} + \delta\vec{\beta}) &\neq A(\delta\vec{\beta}) \cdot A(\vec{\beta}) \\ A(\vec{\beta} + \delta\vec{\beta}) &= R_{\text{tom}}(\Delta\vec{\Omega}) \cdot A(\Delta\vec{\beta}) \cdot A(\vec{\beta}) \end{aligned} \quad (1)$$

where $(\vec{\beta} + \delta\vec{\beta})$ is the direct boost, $\vec{\beta}$ and $\delta\vec{\beta}$ are two successive boosts in the lab frame, $\Delta\vec{\beta}$ and $\Delta\vec{\Omega}$ are, respectively, the successive boost and the angle of rotation with respect to the frame with boost $\vec{\beta}$. $A(\vec{\beta} + \delta\vec{\beta})$, $A(\vec{\beta})$, $A(\delta\vec{\beta})$ and $A(\Delta\vec{\beta})$ are the usual boost matrices for the direct boost and the successive boosts respectively, and $R_{\text{tom}}(\Delta\vec{\Omega})$ is the rotation matrix [5, 6].

This rotation of the space coordinates under the application of successive Lorentz boosts is called Thomas rotation. This phenomenon occurs when a relativistic particle is undergoing accelerated motion. Now since we have to show the acceleration, we added an infinitesimal boost vector $\delta\vec{\beta}$ to the original boost $\vec{\beta}$.

In general, for boosts $\vec{\beta}_1$ and $\vec{\beta}_2$ which are parallel to each other or more specifically boosts corresponding to (1+1)dimensional pure Lorentz transformations, the transformation matrix forms a group which satisfies the equation:

$$A(\vec{\beta}_1) \cdot A(\vec{\beta}_2) = A(\vec{\beta}_{12}) \quad (2)$$

where β_{12} is the velocity composition of two boosts which is given by the equation:

$$\beta_{12} = \frac{\beta_1 + \beta_2}{1 + \beta_1 \cdot \beta_2} \quad (3)$$

But successive boosts which are non collinear, in general, result in Thomas rotation of the space coordinates or in other words, the boosted frames which are accelerating in the sense that their direction is changing will experience Thomas rotation. So the values of the physical quantities obtained by applying just Lorentz transformation are not correct in such cases.

This work is inspired by the ideas discussed in [9–14, 16] but in a slightly different manner. Ungar et al. defined three inertial reference frames Σ , Σ' , and Σ'' in such a way that their corresponding axes are parallel to each other (Σ being the lab frame). It is assumed that the relative velocity of Σ' with respect to Σ and the rel-

* Present address: Department of Pathology, Yale University School of Medicine, New Haven, CT 06510, USA

ative velocity of Σ'' with respect to Σ' is known beforehand. The relativistic velocity composition law can then be used to calculate the velocity of Σ'' with respect to Σ . Usually the velocity of Σ'' with respect to Σ' is not known so the above mentioned approach cannot be used directly. To circumvent this issue, in this paper we present a calculation in which we calculated a matrix A_T [6] from $A(\vec{\beta} + \delta\vec{\beta})$ and $A(-\vec{\beta})$ which contains all the information about relativistic composition of velocities and Thomas rotation.

To our knowledge, the case of non-collinear boosts and its effects on the electromagnetic field tensor has not been discussed in the literature. The aim of this paper is to see how the electromagnetic field tensor transforms with the Lorentz transformations for general three-dimensional boosts and to show that the field tensor in the direct boosted frame $A(\vec{\beta} + \delta\vec{\beta})$ and successive boosted frames $A(\vec{\beta})$ and $A(\delta\vec{\beta})$ are consistent with Thomas rotation.

II. SURVEY OF SOME CONCEPTS OF THE SPECIAL THEORY OF RELATIVITY

A. Lorentz Transformations

For two inertial reference frames Σ and Σ' which have a relative velocity of $\vec{v}$ in such a way that the coordinate axes of Σ are parallel to Σ' and Σ' is moving in the positive x direction as seen from Σ , the position 4-vector of Σ' is related to the position 4-vector of Σ by the standard Lorentz transformation equations [2]:

$$\begin{aligned} x'_0 &= \gamma(x_0 - \beta x_1) \\ x'_1 &= \gamma(x_1 - \beta x_0) \\ x'_2 &= x_2 \\ x'_3 &= x_3 \end{aligned} \quad (4)$$

where

$$x_0 = ct, x_1 = x, x_2 = y, x_3 = z;$$

$$\vec{\beta} = \frac{\vec{v}}{c}, \beta = |\vec{\beta}|;$$

$$\gamma = (1 - \beta^2)^{-1/2}: \text{Lorentz factor}$$

The generalization of Eq. (4) for the relative velocity of Σ' in an arbitrary direction but with the coordinate axes of the two frames still parallel to each other is given by:

$$\begin{aligned} x'_0 &= \gamma(x_0 - \vec{\beta} \cdot \vec{x}) \\ \vec{x}' &= \vec{x} + \frac{(\gamma - 1)}{\beta^2} (\vec{\beta} \cdot \vec{x}) \vec{\beta} - \gamma \vec{\beta} x_0 \end{aligned} \quad (5)$$

B. Addition of Velocities

Consider two inertial reference frames Σ and Σ' such that the relative velocity of Σ' with respect to Σ is $\vec{v}$. A particle is moving in Σ' such that its velocity with respect to Σ' is $\vec{u}'$. The velocity of the particle with respect to Σ is then given by [3]:

$$\begin{aligned} u_{\parallel} &= \frac{u'_{\parallel} + v}{1 + \frac{\vec{v} \cdot \vec{u}'}{c^2}} \\ \vec{u}_{\perp} &= \frac{\vec{u}'_{\perp}}{\gamma_v (1 + \frac{\vec{v} \cdot \vec{u}'}{c^2})} \end{aligned} \quad (6)$$

where $u_{\parallel}$ and $\vec{u}_{\perp}$ refer to the components of velocity parallel and perpendicular, respectively, to $\vec{v}$.

It can be shown that the Lorentz factor of $\vec{v}$, $\vec{u}$, and $\vec{u}'$ are related to each other by

$$\gamma_u = \gamma_v \gamma_{u'} \left(1 + \frac{\vec{v} \cdot \vec{u}'}{c^2} \right) \quad (7)$$

More generally, the velocity composition law for two arbitrary velocities can be written as [9–16]:

$$\vec{u} \oplus \vec{v} = \frac{\vec{u} + \vec{v}}{1 + \frac{\vec{u} \cdot \vec{v}}{c^2}} + \frac{1}{c^2} \left(\frac{\gamma_u}{\gamma_u + 1} \right) \frac{\vec{u} \times (\vec{u} \times \vec{v})}{1 + \frac{\vec{u} \cdot \vec{v}}{c^2}}$$

with

$$\gamma_{u \oplus v} = \gamma_u \gamma_v \left(1 + \frac{\vec{u} \cdot \vec{v}}{c^2} \right) \quad (8)$$

where symbol $\oplus$ refers to the direct sum of the vector space of the velocity vectors.

C. Matrix Representation and Boost Matrix

For the rest of the paper, we will be using matrix methods to calculate Lorentz transformations as they are very convenient to use and are more explicit. All of the equations in Eqs. (4) and (5) can easily be obtained by using the boost matrices for Lorentz transformations. For example, for a boost along the x axis, the boost matrix can be written as [6]:

$$A = \begin{pmatrix} \gamma & -\gamma\beta & 0 & 0 \\ -\gamma\beta & \gamma & 0 & 0 \\ 0 & 0 & 1 & 0 \\ 0 & 0 & 0 & 1 \end{pmatrix} \quad (9)$$

Hence,

$$\begin{pmatrix} ct' \\ x' \\ y' \\ z' \end{pmatrix} = \begin{pmatrix} \gamma & -\gamma\beta & 0 & 0 \\ -\gamma\beta & \gamma & 0 & 0 \\ 0 & 0 & 1 & 0 \\ 0 & 0 & 0 & 1 \end{pmatrix} \begin{pmatrix} ct \\ x \\ y \\ z \end{pmatrix}$$

$$= \begin{pmatrix} \gamma(ct - \beta x) \\ \gamma(x - \beta ct) \\ y \\ z \end{pmatrix} \quad (10)$$

For an arbitrary boost, the general form of the boost matrix A takes a form in which the matrix elements can be written as:

$$A_{00} = \gamma$$

$$A_{0i} = A_{i0} = -\gamma\beta_i$$

$$A_{ij} = A_{ji} = \delta_{ij} + (\gamma - 1)\frac{\beta_i\beta_j}{\beta^2} \quad (11)$$

where δ_{ij} is the kronecker delta. The general form of Eq. (9) can therefore be written as [5]:

$$A = \begin{pmatrix} \gamma & -\gamma\beta_x & -\gamma\beta_y & -\gamma\beta_z \\ -\gamma\beta_x & 1 + (\gamma - 1)\frac{\beta_x^2}{\beta^2} & (\gamma - 1)\frac{\beta_x\beta_y}{\beta^2} & (\gamma - 1)\frac{\beta_x\beta_z}{\beta^2} \\ -\gamma\beta_y & (\gamma - 1)\frac{\beta_y\beta_x}{\beta^2} & 1 + (\gamma - 1)\frac{\beta_y^2}{\beta^2} & (\gamma - 1)\frac{\beta_y\beta_z}{\beta^2} \\ -\gamma\beta_z & (\gamma - 1)\frac{\beta_z\beta_x}{\beta^2} & (\gamma - 1)\frac{\beta_z\beta_y}{\beta^2} & 1 + (\gamma - 1)\frac{\beta_z^2}{\beta^2} \end{pmatrix} \quad (12)$$

D. Set-up

To start with, consider two arbitrary boosts $\vec{\beta}$ and $\delta\vec{\beta}$ in three dimensions:

$$\begin{aligned} \vec{\beta} &= \beta_x\hat{x} + \beta_y\hat{y} + \beta_z\hat{z} \\ \delta\vec{\beta} &= \delta\beta_x\hat{x} + \delta\beta_y\hat{y} + \delta\beta_z\hat{z} \end{aligned} \quad (13)$$




FIG. 2. General boost in three-dimensions. Dotted line represents the projection of $\vec{\beta}$ on the xy -plane.

In order to calculate the boost matrix for various boosts, we will apply a passive transformation which will rotate our lab frame (xy) coordinate axes in such a way

that its x -axis is aligned with $\vec{\beta}$. This rotated frame will hereafter be called the longitudinal-transverse (ℓt) frame.

This whole transformation can be imagined as a product of two rotations: The first rotation is about the z axis by an angle ϕ which will align the x axis along the projection of the boost vector in the xy plane (Fig. 3). The rotation matrix associated with this rotation can be




FIG. 3. Rotation about z axis by an angle ϕ . The new x , y and z axes are called the x_1 , y_1 and z_1 axes respectively.

written as:

$$R_1 = \begin{pmatrix} 1 & 0 & 0 & 0 \\ 0 & \cos \phi & \sin \phi & 0 \\ 0 & -\sin \phi & \cos \phi & 0 \\ 0 & 0 & 0 & 1 \end{pmatrix} \quad (14)$$

The second rotation is about the y_1 axis (Fig. 4)

by an angle $\frac{\pi}{2} - \theta$. The effect of this rotation is that it aligns the x_1 axis to the boost vector $\vec{\beta}$. For the second




FIG. 4. Second rotation about the y_1 axis by an angle $\frac{\pi}{2} - \theta$. x , y , and z axes in this new frame are called the x_2 , y_2 and z_2 axes respectively.

rotation, the rotation matrix can be written as:

$$R_2 = \begin{pmatrix} 1 & 0 & 0 & 0 \\ 0 & \sin \theta & 0 & \cos \theta \\ 0 & 0 & 1 & 0 \\ 0 & -\cos \theta & 0 & \sin \theta \end{pmatrix} \quad (15)$$

The overall effect of the two rotations can be combined in a single transformation matrix R :

$$R = R_2 \cdot R_1 = \begin{pmatrix} 1 & 0 & 0 & 0 \\ 0 & \sin \theta \cos \phi & \sin \theta \sin \phi & \cos \theta \\ 0 & -\sin \phi & \cos \phi & 0 \\ 0 & -\cos \theta \cos \phi & -\cos \theta \sin \phi & \sin \theta \end{pmatrix} \quad (16)$$

It is clear from Fig. 2 that if:

$$\vec{\beta} = \beta_x \hat{x} + \beta_y \hat{y} + \beta_z \hat{z}$$

then

$$\begin{aligned} \cos \theta &= \frac{\beta_z}{\lambda_1} \\ \sin \theta &= \frac{\eta_1}{\lambda_1} \\ \cos \phi &= \frac{\beta_x}{\eta_1} \\ \sin \phi &= \frac{\beta_y}{\eta_1} \end{aligned} \quad (17)$$

where the parameters λ_1 and η_1 are defined in the appendix.

Using Eq. (17), the matrix R can be written as:

$$R = \begin{pmatrix} 1 & 0 & 0 & 0 \\ 0 & \frac{\beta_x}{\lambda_1} & \frac{\beta_y}{\lambda_1} & \frac{\beta_z}{\lambda_1} \\ 0 & -\frac{\beta_y}{\eta_1} & \frac{\beta_x}{\eta_1} & 0 \\ 0 & -\frac{\beta_x \beta_z}{\eta_1 \lambda_1} & -\frac{\beta_y \beta_z}{\eta_1 \lambda_1} & \frac{\eta_1}{\lambda_1} \end{pmatrix} \quad (18)$$

As mentioned earlier, this rotation matrix will transform the lab frame coordinates of any 4-vector (xy -frame) to its coordinates in the rotating frame also called longitudinal-transverse frame (ℓt -frame):

$$\begin{aligned} \vec{\beta}^{\ell t} &= R \cdot \vec{\beta}^{xy} \\ \begin{pmatrix} 0 \\ \beta_x^{\ell t} \\ \beta_y^{\ell t} \\ \beta_z^{\ell t} \end{pmatrix} &= R \cdot \begin{pmatrix} 0 \\ \beta_x^{xy} \\ \beta_y^{xy} \\ \beta_z^{xy} \end{pmatrix} \\ &= \begin{pmatrix} 0 \\ \lambda_1 \\ 0 \\ 0 \end{pmatrix} \end{aligned} \quad (19)$$

where the superscripts ℓt and xy refer to the components in longitudinal-transverse frame and laboratory frame, respectively, and for the sake of simplicity in notation we assumed:

$$\beta_x^{xy} = \beta_x, \quad \beta_y^{xy} = \beta_y, \quad \beta_z^{xy} = \beta_z;$$

Similarly, the infinitesimal boost in the longitudinal-transverse frame is of the form:

$$\begin{aligned} \delta \vec{\beta}^{\ell t} &= R \cdot \delta \vec{\beta}^{xy} \\ \begin{pmatrix} 0 \\ \delta \beta_x^{\ell t} \\ \delta \beta_y^{\ell t} \\ \delta \beta_z^{\ell t} \end{pmatrix} &= R \cdot \begin{pmatrix} 0 \\ \delta \beta_x^{xy} \\ \delta \beta_y^{xy} \\ \delta \beta_z^{xy} \end{pmatrix} \\ &= \begin{pmatrix} 0 \\ \frac{\lambda_2}{\lambda_1} \\ \frac{\lambda_6}{\eta_1} \\ \frac{\lambda_5}{\eta_1 \lambda_1} \end{pmatrix} \end{aligned} \quad (20)$$

where λ_1 , λ_2 , λ_5 , λ_6 and η_1 are defined in the Appendix.

To calculate the $\gamma_{(\vec{\beta} + \delta \vec{\beta})}$ in the ℓt -frame, we have:

$$(\vec{\beta} + \delta \vec{\beta})^{\ell t} = \left(\lambda_1 + \frac{\lambda_2}{\lambda_1} \right) \hat{x} + \frac{\lambda_6}{\eta_1} \hat{y} + \frac{\lambda_5}{\eta_1 \lambda_1} \hat{z}$$

Keeping the terms linear in $\delta \beta$, we get

$$|(\vec{\beta} + \delta \vec{\beta})^{\ell t}|^2 \approx \lambda_1^2 + 2\lambda_2$$

Using the above equation we calculate:

$$\gamma_{(\vec{\beta}+\delta\vec{\beta})} = (1 - \lambda_1^2 - 2\lambda_2)^{-\frac{1}{2}} \\ \approx (1 - \lambda_1^2)^{-\frac{1}{2}} \left[1 + \frac{\lambda_2}{1 - \lambda_1^2} \right]$$

Hence, $\gamma_{(\vec{\beta}+\delta\vec{\beta})}$ can be written as:

$$\gamma_{(\vec{\beta}+\delta\vec{\beta})} \approx \gamma(1 + \gamma^2\lambda_2)$$

where $\gamma = \frac{1}{\sqrt{1-\lambda_1^2}}$ is the Lorentz factor.

Using Eq. (19), the boost matrix for boost $\vec{\beta}^{\ell t}$ can be calculated:

$$A(\vec{\beta})^{\ell t} = \begin{pmatrix} \gamma & -\gamma\lambda_1 & 0 & 0 \\ -\gamma\lambda_1 & \gamma & 0 & 0 \\ 0 & 0 & 1 & 0 \\ 0 & 0 & 0 & 1 \end{pmatrix} \quad (21)$$

Similarly, using Eqs. (19), (20), to the first order in $\delta\beta$, the boost matrix for the direct boost $\vec{\beta} + \delta\vec{\beta}$ in the ℓt -frame can be written as:

$$A(\vec{\beta}+\delta\vec{\beta})^{\ell t} = \begin{pmatrix} \gamma + \gamma^3\lambda_2 & -\frac{\gamma(\lambda_1^2 + \gamma^2\lambda_2)}{\lambda_1} & -\frac{\gamma\lambda_6}{\eta_1} & -\frac{\gamma\lambda_5}{\eta_1\lambda_1} \\ -\frac{\gamma(\lambda_1^2 + \gamma^2\lambda_2)}{\lambda_1} & \gamma + \gamma^3\lambda_2 & \frac{(\gamma-1)\lambda_6}{\eta_1\lambda_1} & \frac{(\gamma-1)\lambda_5}{\eta_1\lambda_1^2} \\ -\frac{\gamma\lambda_6}{\eta_1} & \frac{(\gamma-1)\lambda_6}{\eta_1\lambda_1} & 1 & 0 \\ -\frac{\gamma\lambda_5}{\eta_1\lambda_1} & \frac{(\gamma-1)\lambda_5}{\eta_1\lambda_1^2} & 0 & 1 \end{pmatrix} \quad (22)$$

$$F^{\ell t} = \begin{pmatrix} 0 & \frac{-\beta_x E_x - \beta_y E_y - \beta_z E_z}{\lambda_1} & \frac{\beta_y E_x - \beta_x E_y}{\eta_1} & \frac{-E_z \beta_x^2 + \beta_z E_x \beta_x + \beta_y (\beta_z E_y - \beta_y E_z)}{\eta_1 \lambda_1} \\ \frac{\beta_x E_x + \beta_y E_y + \beta_z E_z}{\lambda_1} & 0 & \frac{(B_x \beta_x + B_y \beta_y) \beta_z - B_z \eta_1^2}{\eta_1 \lambda_1} & \frac{B_y \beta_x - B_x \beta_y}{\eta_1} \\ \frac{\beta_x E_y - \beta_y E_x}{\eta_1} & \frac{B_z \eta_1^2 - (B_x \beta_x + B_y \beta_y) \beta_z}{\eta_1 \lambda_1} & 0 & \frac{-B_x \beta_x - B_y \beta_y - B_z \beta_z}{\lambda_1} \\ \frac{E_z \beta_x^2 - \beta_x \beta_z E_x + \beta_y (\beta_y E_z - \beta_z E_y)}{\eta_1 \lambda_1} & \frac{B_x \beta_y - B_y \beta_x}{\eta_1} & \frac{B_x \beta_x + B_y \beta_y + B_z \beta_z}{\lambda_1} & 0 \end{pmatrix}$$

To the electromagnetic field tensor obtained in Eq. (24), we will apply boost matrix for the first successive boost $\vec{\beta}^{\ell t}$ and the direct boost $(\vec{\beta} + \delta\vec{\beta})^{\ell t}$ using the well-known equation [8]:

$$F' = A \cdot F \cdot A^T \quad (25)$$

where F' and F are the electromagnetic field tensors in

III. TRANSFORMATIONS OF THE ELECTROMAGNETIC FIELD TENSOR

The main idea of this paper is to see how the electromagnetic fields transform relativistically when there is an accelerated motion. It can be further divided into transformations in the longitudinal-transverse and lab frame.

A. Longitudinal-Transverse ℓt -Frame

To see the effects on electromagnetic fields, we first need to bring the electromagnetic field tensor to the rotating ℓt -frame so that all the boosts and electromagnetic fields are in the same frame to start with. The electromagnetic field tensor $F^{\mu\nu}$ in the lab frame is given by [7]:

$$F^{\mu\nu} = \begin{pmatrix} 0 & -E_x & -E_y & -E_z \\ E_x & 0 & -B_z & B_y \\ E_y & B_z & 0 & -B_x \\ E_z & -B_y & B_x & 0 \end{pmatrix} \quad (23)$$

For the rest of the paper we will write $F^{\mu\nu} = F$.

To get the field tensor in the ℓt -frame, we can apply the rotation matrix R on $F^{\mu\nu}$:

$$F^{\ell t} = R \cdot F \cdot R^T \quad (24)$$

where the superscript T refers to matrix transpose. After plugging in the values of R and F from Eqs. (18) and (23), we can write $F^{\ell t}$ as:

the boosted frame and the lab frame (or any inertial frame) respectively and A is the boost matrix.

For boost $\vec{\beta}^{\ell t}$, the transformation of $F^{\ell t}$ can be calculated using Eqs. (21), (24) and (25):

$$(F')^{\ell t} = A(\vec{\beta}^{\ell t}) \cdot F^{\ell t} \cdot (A(\vec{\beta}^{\ell t}))^T$$

The following table has the elements of $(F')^{\ell t}$ after matrix multiplication:

Electromagnetic fields in Table I are consistent with the

standard field transformation equations [8, 12].

$$\vec{E}' = \gamma \left(\vec{E} + \vec{\beta} \times \vec{B} \right) - \frac{\gamma^2}{\gamma + 1} \vec{\beta} (\vec{\beta} \cdot \vec{E})$$

$(F'^{10})^{\ell t}$	$(E'_x)^{\ell t}$	$\frac{\beta_x E_x + \beta_y E_y + \beta_z E_z}{\lambda_1}$
$(F'^{20})^{\ell t}$	$(E'_y)^{\ell t}$	$\frac{\gamma(-B_z \eta_1^2 + B_x \beta_x \beta_z + B_y \beta_y \beta_z - E_x \beta_y + \beta_x E_y)}{\eta_1}$
$(F'^{30})^{\ell t}$	$(E'_z)^{\ell t}$	$\frac{\gamma(B_y \beta_x \lambda_1^2 - B_x \beta_y \lambda_1^2 + \beta_x^2 E_z - \beta_x E_x \beta_z - \beta_y E_y \beta_z + \beta_y^2 E_z)}{\eta_1 \lambda_1}$
$(F'^{32})^{\ell t}$	$(B'_x)^{\ell t}$	$\frac{B_x \beta_x + B_y \beta_y + B_z \beta_z}{\lambda_1}$
$(F'^{13})^{\ell t}$	$(B'_y)^{\ell t}$	$\frac{\gamma(B_y \beta_x - B_x \beta_y + \beta_x^2 E_z - \beta_x E_x \beta_z - \beta_y E_y \beta_z + \beta_y^2 E_z)}{\eta_1}$
$(F'^{21})^{\ell t}$	$(B'_z)^{\ell t}$	$\frac{\gamma(B_z \eta_1^2 - B_x \beta_x \beta_z - B_y \beta_y \beta_z - \beta_x^3 E_y + \beta_x^2 E_x \beta_y - \beta_x \beta_y^2 E_y + E_x \beta_y^3 - \beta_x E_y \beta_z^2 + E_x \beta_y \beta_z^2)}{\eta_1 \lambda_1}$

TABLE I. Expressions for the indicated components of the electromagnetic field tensor after being transformed by the first boost $\vec{\beta}^{\ell t}$ in the longitudinal-transverse frame.

$$\vec{B}' = \gamma \left(\vec{B} - \vec{\beta} \times \vec{E} \right) - \frac{\gamma^2}{\gamma + 1} \vec{\beta} (\vec{\beta} \cdot \vec{B}) \quad (26)$$

Similarly, for the direct boost $(\vec{\beta} + \delta\vec{\beta})^{\ell t}$, the electromagnetic field tensor transformation is given by:

$$(F'')^{\ell t} = A((\vec{\beta} + \delta\vec{\beta})^{\ell t}) \cdot F^{\ell t} \cdot A((\vec{\beta} + \delta\vec{\beta})^{\ell t})^T$$

After simplification and keeping terms to linear order in $\delta\beta$, $(F'')^{\ell t}$ can be calculated and the detailed expressions of its elements are provided in the Appendix (Section A.1).

Because of the way we set up the problem, the electromagnetic field tensor described by the direct boost $(\vec{\beta} + \delta\vec{\beta})^{\ell t}$ already consists of rotations. To get the electromagnetic fields which do not have any rotations (pure Lorentz boost) [6], we will use the successive boosts. As mentioned earlier in the Introduction, we will calculate a matrix A_T :

$$A_T = A(\vec{\beta} + \delta\vec{\beta}) \cdot A(-\vec{\beta}) \quad (27)$$

For the ℓt -frame, A_T looks like:

$$A_T^{\ell t} = \begin{pmatrix} 1 & \frac{-\gamma^2 \lambda_2}{\lambda_1} & -\frac{\gamma \lambda_6}{\eta_1} & -\frac{\gamma \lambda_5}{\eta_1 \lambda_1} \\ \frac{-\gamma^2 \lambda_2}{\lambda_1} & 1 & \frac{(\gamma-1) \lambda_6}{\eta_1 \lambda_1} & \frac{(\gamma-1) \lambda_5}{\eta_1 \lambda_1^2} \\ -\frac{\gamma \lambda_6}{\eta_1} & -\frac{(\gamma-1) \lambda_6}{\eta_1 \lambda_1} & 1 & 0 \\ -\frac{\gamma \lambda_5}{\eta_1 \lambda_1} & -\frac{(\gamma-1) \lambda_5}{\eta_1 \lambda_1^2} & 0 & 1 \end{pmatrix} \quad (28)$$

The matrix A_T contains all the information regarding relativistic composition of velocities and Thomas rotation which can be seen if we write A_T as [6]:

$$\begin{aligned} A_T^{\ell t} &= A(\Delta\vec{\beta})^{\ell t} \cdot R_{\text{tom}}(\Delta\vec{\Omega})^{\ell t} \\ &= \left(I - \Delta\vec{\beta}^{\ell t} \cdot \vec{K} \right) \cdot \left(I - \Delta\vec{\Omega}^{\ell t} \cdot \vec{S} \right) \end{aligned} \quad (29)$$

where $\Delta\vec{\beta}^{\ell t}$ = successive boost with respect to frame with boost

$\vec{\beta}$; $\Delta\vec{\Omega}^{\ell t} = \left[\left(\frac{\gamma-1}{\beta^2} \right) \vec{\beta}^{\ell t} \times \delta\vec{\beta}^{\ell t} \right]$ is the angle of rotation associated with Thomas rotation.

It can be easily shown that if the boosts and rotations are infinitesimal then:

$$A(\Delta\vec{\beta}) \cdot R_{\text{tom}}(\Delta\vec{\Omega}) = R_{\text{tom}}(\Delta\vec{\Omega}) \cdot A(\Delta\vec{\beta})$$

Matrices $\vec{K}$ and $\vec{S}$ are the generators of Lorentz boosts and rotations respectively:

$$\begin{aligned} K_1 &= \begin{pmatrix} 0 & 1 & 0 & 0 \\ 1 & 0 & 0 & 0 \\ 0 & 0 & 0 & 0 \\ 0 & 0 & 0 & 0 \end{pmatrix}, & K_2 &= \begin{pmatrix} 0 & 0 & 1 & 0 \\ 0 & 0 & 0 & 0 \\ 1 & 0 & 0 & 0 \\ 0 & 0 & 0 & 0 \end{pmatrix}, \\ K_3 &= \begin{pmatrix} 0 & 0 & 0 & 1 \\ 0 & 0 & 0 & 0 \\ 0 & 0 & 0 & 0 \\ 1 & 0 & 0 & 0 \end{pmatrix}, & S_1 &= \begin{pmatrix} 0 & 0 & 0 & 0 \\ 0 & 0 & 0 & 0 \\ 0 & 0 & 0 & -1 \\ 0 & 0 & 1 & 0 \end{pmatrix}, \\ S_2 &= \begin{pmatrix} 0 & 0 & 0 & 0 \\ 0 & 0 & 0 & 1 \\ 0 & 0 & 0 & 0 \\ 0 & -1 & 0 & 0 \end{pmatrix}, & S_3 &= \begin{pmatrix} 0 & 0 & 0 & 0 \\ 0 & 0 & -1 & 0 \\ 0 & 1 & 0 & 0 \\ 0 & 0 & 0 & 0 \end{pmatrix} \end{aligned}$$

Extracting the matrix form of $A(\Delta\vec{\beta}^{\ell t})$ and $R_{\text{tom}}(\Delta\vec{\Omega}^{\ell t})$ from A_T , we get:

$$A(\Delta\vec{\beta})^{\ell t} = \begin{pmatrix} 1 & \frac{-\gamma^2 \lambda_2}{\lambda_1} & -\frac{\gamma \lambda_6}{\eta_1} & -\frac{\gamma \lambda_5}{\eta_1 \lambda_1} \\ \frac{-\gamma^2 \lambda_2}{\lambda_1} & 1 & 0 & 0 \\ -\frac{\gamma \lambda_6}{\eta_1} & 0 & 1 & 0 \\ -\frac{\gamma \lambda_5}{\eta_1 \lambda_1} & 0 & 0 & 1 \end{pmatrix}$$

$$R_{\text{tom}}(\Delta\vec{\Omega})^{\ell t} = \begin{pmatrix} 1 & 0 & 0 & 0 \\ 0 & 1 & \frac{(\gamma-1) \lambda_6}{\eta_1 \lambda_1} & \frac{(\gamma-1) \lambda_5}{\eta_1 \lambda_1^2} \\ 0 & -\frac{(\gamma-1) \lambda_6}{\eta_1 \lambda_1} & 1 & 0 \\ 0 & -\frac{(\gamma-1) \lambda_5}{\eta_1 \lambda_1^2} & 0 & 1 \end{pmatrix} \quad (30)$$

In order to find the electromagnetic fields due to pure Lorentz boosts, we calculate the electromagnetic field tensor due to the successive boosts $\vec{\beta}^{\ell t}$ and $\Delta\vec{\beta}^{\ell t}$:

$$(F''')^{\ell t} = A(\Delta\vec{\beta})^{\ell t} \cdot A(\vec{\beta})^{\ell t} \cdot F^{\ell t} \cdot (A(\vec{\beta})^{\ell t})^T \cdot (A(\Delta\vec{\beta})^{\ell t})^T \\ = A(\Delta\vec{\beta})^{\ell t} \cdot (F')^{\ell t} \cdot (A(\Delta\vec{\beta})^{\ell t})^T \quad (31)$$

After simplification and keeping the terms which are linear in $\delta\beta$, we get the matrix $(F''')^{\ell t}$ whose elements are provided in the Appendix (Section A.2).

It should be noted that since $(F''')^{\ell t}$ and $(F'')^{\ell t}$ are different from each other by just a rotation, so $(F''')^{\ell t}$ can be obtained by operating an inverse Thomas rotation on $(F'')^{\ell t}$. In fact, we used this as a check for verifying if the expressions of electromagnetic fields calculated using Eq. (32) are correct.

$$(F''')^{\ell t} = R_{\text{tom}}(-\Delta\vec{\Omega})^{\ell t} \cdot (F'')^{\ell t} \cdot (R_{\text{tom}}(-\Delta\vec{\Omega})^{\ell t})^T \quad (32)$$

B. Laboratory xy -Frame

After getting the expressions of electromagnetic fields in the ℓt -frame obtained by different boosts, we now calculate the electromagnetic fields by the same boosts with respect to the lab frame. The overall approach stays the same but all the boost matrices are needed to be transformed in the xy -frame before being used to calculate the electromagnetic field tensor. Another way of calculating the electromagnetic field tensor is to directly transform the field tensors obtained in ℓt -frame.

In order to calculate the electromagnetic field tensor for various boosts in the lab xy -frame, we will just use the field tensor F as defined in Eq. (23). Since R is the rotation matrix for passive coordinate transformations (18), we have:

$$R \cdot R^T = R^T \cdot R = I \quad (33)$$

therefore we can write the electromagnetic tensors and boost matrices in the lab xy -frame as:

$$F^{xy} = R^T \cdot F^{\ell t} \cdot R \\ A^{xy} = R^T \cdot A^{\ell t} \cdot R \quad (34)$$

After matrix multiplication, $A(\vec{\beta})^{xy}$ can be written as:

$$A(\vec{\beta})^{xy} = \begin{pmatrix} \gamma & -\gamma\beta_x & -\gamma\beta_y & -\gamma\beta_z \\ -\gamma\beta_x & \frac{\gamma\beta_x^2 + \beta_y^2 + \beta_z^2}{\lambda_1^2} & \frac{(\gamma-1)\beta_x\beta_y}{\lambda_1^2} & \frac{(\gamma-1)\beta_x\beta_z}{\lambda_1^2} \\ -\gamma\beta_y & \frac{(\gamma-1)\beta_x\beta_y}{\lambda_1^2} & \frac{\beta_x^2 + \gamma\beta_y^2 + \beta_z^2}{\lambda_1^2} & \frac{(\gamma-1)\beta_y\beta_z}{\lambda_1^2} \\ -\gamma\beta_z & \frac{(\gamma-1)\beta_x\beta_z}{\lambda_1^2} & \frac{(\gamma-1)\beta_y\beta_z}{\lambda_1^2} & \frac{\beta_x^2 + \beta_y^2 + \gamma\beta_z^2}{\lambda_1^2} \end{pmatrix}$$

which is in agreement with Eq. (12) if we substitute in

$$\vec{\beta} = \vec{\beta}^{xy} = \beta_x \hat{x} + \beta_y \hat{y} + \beta_z \hat{z}$$

Using Eqs. (25) and (34) we can calculate the electromagnetic field tensor $(F')^{xy}$ which corresponds to the boost $\vec{\beta}^{xy}$:

$(F'^{10})^{xy}$	$(E'_x)^{xy}$	$\gamma E_x + \gamma(B_z\beta_y - B_y\beta_z) - \frac{\gamma^2\beta_x(\beta_x E_x + \beta_y E_y + \beta_z E_z)}{\gamma+1}$
$(F'^{20})^{xy}$	$(E'_y)^{xy}$	$\gamma E_y + \gamma(B_x\beta_z - B_z\beta_x) - \frac{\gamma^2\beta_y(\beta_x E_x + \beta_y E_y + \beta_z E_z)}{\gamma+1}$
$(F'^{30})^{xy}$	$(E'_z)^{xy}$	$\gamma E_z + \gamma(B_y\beta_x - B_x\beta_y) - \frac{\gamma^2\beta_z(\beta_x E_x + \beta_y E_y + \beta_z E_z)}{\gamma+1}$
$(F'^{32})^{xy}$	$(B'_x)^{xy}$	$\gamma B_x + \gamma(E_y\beta_z - \beta_y E_z) - \frac{\gamma^2\beta_x(B_x\beta_x + B_y\beta_y + B_z\beta_z)}{\gamma+1}$
$(F'^{13})^{xy}$	$(B'_y)^{xy}$	$\gamma B_y + \gamma(E_z\beta_x - \beta_z E_x) - \frac{\gamma^2\beta_y(B_x\beta_x + B_y\beta_y + B_z\beta_z)}{\gamma+1}$
$(F'^{21})^{xy}$	$(B'_z)^{xy}$	$\gamma B_z + \gamma(E_x\beta_y - \beta_x E_y) - \frac{\gamma^2\beta_z(B_x\beta_x + B_y\beta_y + B_z\beta_z)}{\gamma+1}$

TABLE II. Expressions for the indicated components of the electromagnetic field tensor after being transformed by the first boost $\vec{\beta}^{xy}$ in the laboratory frame.

Again, the components of the electromagnetic field

tensor in Table II can be verified from the standard field

transformations as shown in Eq. (26).

Similarly, for the direct boost $(\vec{\beta} + \delta\vec{\beta})^{xy}$, we can use Eq. (34) to calculate the boost matrix. The detailed

expression of $A(\vec{\beta} + \delta\vec{\beta})^{xy}$ is too long to write here but it shares the same features as [6] which can be seen if we let $\delta\beta_z = \beta_y = \beta_z = 0$:

$$A(\vec{\beta} + \delta\vec{\beta})^{xy} = \begin{pmatrix} \gamma + \gamma^3\beta_x\delta\beta_x & -(\gamma\beta_x + \gamma^3\delta\beta_x) & -\gamma\delta\beta_y & 0 \\ -(\gamma\beta_x + \gamma^3\delta\beta_x) & \gamma + \gamma^3\beta_x\delta\beta_x & \left(\frac{\gamma-1}{\beta_x^2}\right)\beta_x\delta\beta_y & 0 \\ -\gamma\delta\beta_y & \left(\frac{\gamma-1}{\beta_x^2}\right)\beta_x\delta\beta_y & 0 & 1 \\ 0 & 0 & 0 & 1 \end{pmatrix} \quad (35)$$

The above matrix is identical in form to the one shown in [6]. After calculating the boost matrix Eq. (35), we can again use Eq. (25) to calculate the electromagnetic field tensor in the direct boosted frame with respect to the laboratory frame whose detailed expressions are provided in the Appendix (Section B.1).

In order to calculate electromagnetic fields in the inertial frames which are boosted upon by pure Lorentz boosts (no rotation), we use successive boosts $\vec{\beta}$ and $\Delta\vec{\beta}$. For that we have to calculate the expression of A_T^{xy} first as done in Eq. (27) which is:

$$A_T^{xy} = \begin{pmatrix} 1 & -\frac{1}{\lambda_1^2}(\gamma\lambda_3 + \gamma^2\beta_x\lambda_2) & -\frac{1}{\lambda_1^2}(\gamma\lambda_4 + \gamma^2\beta_y\lambda_2) & -\frac{1}{\lambda_1^2}(\gamma\lambda_5 + \gamma^2\beta_z\lambda_2) \\ -\frac{1}{\lambda_1^2}(\gamma\lambda_3 + \gamma^2\beta_x\lambda_2) & 1 & \frac{(\gamma-1)\lambda_6}{\lambda_1^2} & -\frac{(\gamma-1)\lambda_8}{\lambda_1^2} \\ -\frac{1}{\lambda_1^2}(\gamma\lambda_4 + \gamma^2\beta_y\lambda_2) & -\frac{(\gamma-1)\lambda_6}{\lambda_1^2} & 1 & \frac{(\gamma-1)\lambda_7}{\lambda_1^2} \\ -\frac{1}{\lambda_1^2}(\gamma\lambda_5 + \gamma^2\beta_z\lambda_2) & \frac{(\gamma-1)\lambda_8}{\lambda_1^2} & -\frac{(\gamma-1)\lambda_7}{\lambda_1^2} & 1 \end{pmatrix} \quad (36)$$

As we know from Eq. (29), $A(\Delta\vec{\beta})^{xy}$ and $R_{\text{tom}}(\Delta\vec{\Omega})^{xy}$

can be extracted from A_T^{xy} which can be written as:

$$A(\Delta\vec{\beta})^{xy} = \begin{pmatrix} 1 & -\frac{1}{\lambda_1^2}(\gamma\lambda_3 + \gamma^2\beta_x\lambda_2) & -\frac{1}{\lambda_1^2}(\gamma\lambda_4 + \gamma^2\beta_y\lambda_2) & -\frac{1}{\lambda_1^2}(\gamma\lambda_5 + \gamma^2\beta_z\lambda_2) \\ -\frac{1}{\lambda_1^2}(\gamma\lambda_3 + \gamma^2\beta_x\lambda_2) & 1 & 0 & 0 \\ -\frac{1}{\lambda_1^2}(\gamma\lambda_4 + \gamma^2\beta_y\lambda_2) & 0 & 1 & 0 \\ -\frac{1}{\lambda_1^2}(\gamma\lambda_5 + \gamma^2\beta_z\lambda_2) & 0 & 0 & 1 \end{pmatrix}$$

$$R_{\text{tom}}(\Delta\vec{\Omega})^{xy} = \begin{pmatrix} 1 & 0 & 0 & 0 \\ 0 & 1 & \frac{(\gamma-1)\lambda_6}{\lambda_1^2} & -\frac{(\gamma-1)\lambda_8}{\lambda_1^2} \\ 0 & -\frac{(\gamma-1)\lambda_6}{\lambda_1^2} & 1 & \frac{(\gamma-1)\lambda_7}{\lambda_1^2} \\ 0 & \frac{(\gamma-1)\lambda_8}{\lambda_1^2} & -\frac{(\gamma-1)\lambda_7}{\lambda_1^2} & 1 \end{pmatrix} \quad (37)$$

where λ_i , ($i = 1, 2, \dots, 8$) and η_1 are defined in the appendix.

Using Eq. (37) we can now calculate electromagnetic fields due to pure Lorentz boosts whose detailed expressions are provided in the Appendix (Section B.2).

$$(F''')^{xy} = A(\Delta\vec{\beta})^{xy} \cdot A(\vec{\beta})^{xy} \cdot F^{xy} \cdot (A(\vec{\beta})^{xy})^T \cdot (A(\Delta\vec{\beta})^{xy})^T$$

$$= A(\Delta\vec{\beta})^{xy} \cdot (F')^{xy} \cdot (A(\Delta\vec{\beta})^{xy})^T \quad (38)$$

IV. VALIDATION OF RESULTS

All the framework that we have constructed can be verified by two ways:

1. Verifying the form of boost matrices and electromagnetic field tensor for some special cases as dis-

cussed in [6, 7].

2. Applying this whole formalism on a 4-vector like position.

For the first approach, in order to see the identical nature of results we will assume the special case of $\beta_y = \beta_z = \delta\beta_z = 0$. Applying this assumption on Eqs. (21) and (22) will give us:

$$A(\vec{\beta})^{\ell t} = \begin{pmatrix} \gamma & -\gamma\beta_x & 0 & 0 \\ -\gamma\beta_x & \gamma & 0 & 0 \\ 0 & 0 & 1 & 0 \\ 0 & 0 & 0 & 1 \end{pmatrix}$$

$$A(\vec{\beta} + \delta\vec{\beta})^{\ell t} = \begin{pmatrix} \gamma + \gamma^3\beta_x\delta\beta_x & -(\gamma\beta_x + \gamma^3\delta\beta_x) & -\gamma\delta\beta_y & 0 \\ -(\gamma\beta_x + \gamma^3\delta\beta_x) & \gamma + \gamma^3\beta_x\delta\beta_x & \left(\frac{\gamma-1}{\beta_x}\right)\delta\beta_y & 0 \\ -\gamma\delta\beta_y & \left(\frac{\gamma-1}{\beta_x}\right)\delta\beta_y & 0 & 1 \\ 0 & 0 & 0 & 1 \end{pmatrix} \quad (39)$$

Similarly, $A_T^{\ell t}$ can be reduced to a familiar result [6]:

$$A_T^{\ell t} = \begin{pmatrix} 1 & -\gamma^2\delta\beta_x & \frac{-\gamma\delta\beta_y}{\beta_x} & 0 \\ -\gamma^2\delta\beta_x & 1 & \frac{(\gamma-1)\delta\beta_y}{\beta_x} & 0 \\ -\gamma\delta\beta_y & -\frac{(\gamma-1)\delta\beta_y}{\beta_x} & 1 & 0 \\ 0 & 0 & 0 & 1 \end{pmatrix} \quad (40)$$

In the lab xy -frame, we get the exact same results as Eqs. (39) and (40) for the above mentioned special case. This makes perfect sense since letting $\beta_y = \beta_z = \delta\beta_z = 0$ would just make the original passive coordinate transformations redundant and both the ℓt - and xy -frames will be identical.

To see if the matrix for Thomas rotation $R_{\text{tom}}(\Delta\vec{\Omega})$

is correct we can directly calculate it from its definition:

$$R_{\text{tom}}(\Delta\vec{\Omega}) = \left(I - \Delta\vec{\Omega} \cdot \vec{S} \right) \quad (41)$$

where

$$\Delta\vec{\Omega} = \left[\left(\frac{\gamma-1}{\beta^2} \right) \vec{\beta} \times \delta\vec{\beta} \right]$$

The Thomas rotation matrix calculated from the Eq. (41) using the corresponding representations of the boost vectors in $\ell t/xy$ -frames matches with Eqs. (30) and (37).

For the verification of Electromagnetic Field Tensors, we can calculate them in different ways. As an example, we calculated $(F''')^{xy}$ using:

$$\begin{aligned} (F''')^{xy} &= A(\Delta\vec{\beta})^{xy} \cdot A(\vec{\beta})^{xy} \cdot F^{xy} \cdot (A(\vec{\beta})^{xy})^T \cdot (A(\Delta\vec{\beta})^{xy})^T \\ &= R_{\text{tom}}(-\Delta\vec{\Omega})^{xy} \cdot (F'')^{xy} \cdot (R_{\text{tom}}(-\Delta\vec{\Omega})^{xy})^T \\ &= R^T \cdot (F''')^{\ell t} \cdot R \end{aligned}$$

All three equations yielded same results. Similar verification also holds for other electromagnetic field tensors involved.

Our second approach for verification is based on Un-

gar et al. [9, 10, 16] in which we apply direct boost $(\vec{\beta} + \delta\vec{\beta})$ and successive boosts $\vec{\beta}$ and $\Delta\vec{\beta}$ to a position 4-vector. We can check if the results are consistent and

share the same overall features as the electromagnetic field tensor. To see that we start with a general position 4-vector in the lab frame and for simplicity, we ignore the time component in the position 4-vector:

$$(r)^{xy} = \begin{pmatrix} 0 \\ x \\ y \\ z \end{pmatrix} \quad (42)$$

Transforming it in the ℓt - frame using the rotation matrix R (18), we get:

$$(r)^{\ell t} = R \cdot r^{xy} = \begin{pmatrix} 0 \\ \frac{x\beta_x + y\beta_y + z\beta_z}{\lambda_1} \\ \frac{y\beta_x - x\beta_y}{\eta_1} \\ \frac{z\beta_x^2 - x\beta_z\beta_x + \beta_y(z\beta_y - y\beta_z)}{\eta_1\lambda_1} \end{pmatrix} \quad (43)$$

We can calculate the expression of $(r)^{\ell t}$ transformed by the first successive boost $\vec{\beta}^{\ell t}$ using Eq. (21) in the same way we calculated the electromagnetic field tensor $F^{\mu\nu}$:

$$(r')^{\ell t} = A(\vec{\beta})^{\ell t} \cdot (r)^{\ell t} = \begin{pmatrix} -\gamma(x\beta_x + y\beta_y + z\beta_z) \\ \frac{\gamma(x\beta_x + y\beta_y + z\beta_z)}{\lambda_1} \\ \frac{y\beta_x - x\beta_y}{\eta_1} \\ \frac{z\beta_x^2 - x\beta_z\beta_x + \beta_y(z\beta_y - y\beta_z)}{\eta_1\lambda_1} \end{pmatrix} \quad (44)$$

which is nothing but the standard Lorentz transformation of coordinates. Similarly, for the direct boost $(\vec{\beta} + \delta\vec{\beta})^{\ell t}$ and successive boosts $\vec{\beta}^{\ell t}$ and $\Delta\vec{\beta}^{\ell t}$, after letting $\beta_z = \delta\beta_z = 0$ for simplicity, we have:

$$\begin{aligned} (r'')^{\ell t} &= A(\vec{\beta} + \delta\vec{\beta})^{\ell t} \cdot (r)^{\ell t} \\ &= \begin{pmatrix} -\frac{\gamma(x\beta_x^3 + (x\delta\beta_x\gamma^2 + y\beta_y + y\delta\beta_y)\beta_x^2 + \beta_y(x\beta_y + (\gamma^2 - 1)(y\delta\beta_x + x\delta\beta_y))\beta_x + \beta_y^2(y\delta\beta_y\gamma^2 + y\beta_y + x\delta\beta_x))}{\eta_1^2} \\ \frac{(\gamma - 1)(y\beta_x - x\beta_y)(\beta_x\delta\beta_y - \beta_y\delta\beta_x) + (x\beta_x + y\beta_y)\eta_1^2((\beta_x\delta\beta_x + \beta_y\delta\beta_y)\gamma^3 + \gamma)}{\eta_1^3} \\ \frac{y\beta_x^3 - x(\beta_y - (\gamma - 1)\delta\beta_y)\beta_x^2 + \beta_y(y\beta_y - (\gamma - 1)(x\delta\beta_x - y\delta\beta_y))\beta_x - \beta_y^2(x\beta_y + y(\gamma - 1)\delta\beta_x)}{\eta_1^3} \\ z \end{pmatrix} \\ (r''')^{\ell t} &= A(\Delta\vec{\beta})^{\ell t} \cdot A(\vec{\beta})^{\ell t} \cdot (r)^{\ell t} \\ &= A(\Delta\vec{\beta})^{\ell t} \cdot (r')^{\ell t} \\ &= \begin{pmatrix} \gamma \left(-\frac{(x\beta_x + y\beta_y)(\beta_x\delta\beta_x + \beta_y\delta\beta_y)\gamma^2}{\eta_1^2} - x\beta_x - y\beta_y - \frac{(y\beta_x - x\beta_y)\lambda_6}{\eta_1^2} \right) \\ \frac{\gamma(x\beta_x + y\beta_y)(\beta_x\delta\beta_x\gamma^2 + \beta_y\delta\beta_y\gamma^2 + 1)}{\eta_1} \\ \frac{x\gamma^2\delta\beta_y\beta_x^2 + (\beta_y(y\delta\beta_y - x\delta\beta_x)\gamma^2 + y)\beta_x - \beta_y(y\beta_y\delta\beta_x\gamma^2 + x)}{\eta_1} \\ z \end{pmatrix} \end{aligned} \quad (45)$$

One way to check if Eqs. (44) and (45) are correct is to show that the invariant interval ds^2 [4]:

remains the same, where $g_{\mu\nu}$ is the metric tensor:

$$g_{\mu\nu} = \begin{pmatrix} 1 & 0 & 0 & 0 \\ 0 & -1 & 0 & 0 \\ 0 & 0 & -1 & 0 \\ 0 & 0 & 0 & -1 \end{pmatrix}$$

In our case we are concerned with the invariance of

$$s^2 = x_0^2 - x_1^2 - x_2^2 - x_3^2 \quad (47)$$

To see if that is the case, we can apply Eq. (47) to $(r')^{\ell t}$,

$$\begin{aligned} ds^2 &= g_{\mu\nu} dx^\mu dx^\nu \\ &= (dx^0)^2 - (dx^1)^2 - (dx^2)^2 - (dx^3)^2 \end{aligned} \quad (46)$$

$(r'')^{\ell t}$ and $(r''')^{\ell t}$ calculated above. The invariant

$$s^2 = -x^2 - y^2 - z^2$$

indeed stays the same for each case. This makes sense since we ignored the time component.

Similar results can be obtained for the position 4-vector r in the lab xy -frame and it can be easily proved that the invariant does not change. We also compare our approach with Ungar's in the Appendix (Section C).

V. CONCLUSION

The work presented in this paper is another confirmation of the fact that two successive boosts are not equal to a single direct boost. In the case of the electromagnetic field, just applying the usual electromagnetic field transformation equations will not result in the correct form of electromagnetic fields in the case of non-collinear boosts (accelerating frames) as Thomas rotation must be included.

Apart from the validations made in the previous section we will see if the electromagnetic field tensors in the direct boosted frame $\vec{\beta} + \delta\vec{\beta}$ and the successively boosted frames $\vec{\beta}$ and $\Delta\vec{\beta}$ are consistent with the Thomas rotation. To see that we can take the difference between the corresponding elements of F'' and F''' in both the longitudinal-transverse ℓt and lab xy -frames.

After taking the difference of the electromagnetic field tensors F'' and F''' we found that

$$(F'')_{ij} - (F''')_{ij} \propto (\gamma - 1) \quad (48)$$

for both ℓt - and xy -frames. This makes sense because both F'' and F''' just differ by Thomas rotation. Although taking the difference of F'' and F''' is not very significant physically it does show what we expected.

To our knowledge, this is the first time that someone has calculated the expressions of the electromagnetic fields in the frames corresponding to general three-dimensional non-collinear boosts.

One application of this work concerns the calculation of shifts in the Larmor frequency of highly relativistic particles moving through non-uniform magnetic and electric fields. Such a formalism was developed for the motion of non-relativistic particles [17–19]; however, this formalism is not directly applicable to relativistic particles because the formalism assumes the electromagnetic fields are known in the particle rest frame. For a highly relativistic particle undergoing acceleration (e.g.,

relativistic charged particles stored by electromagnetic fields within a circular storage ring), one can then apply the formalism developed here in this paper to determine the electromagnetic fields in an appropriate reference frame, where any residual motion of the particle is then non-relativistic, and then proceed to calculate the frequency shifts per the formalism of [17–19].

Acknowledgments

This material is based upon work supported by the U.S. Department of Energy, Office of Science, Office of Nuclear Physics, under Award Number DE-SC0014622.

VI. APPENDIX

We begin by recalling that the electromagnetic field tensor $F^{\mu\nu}$ is an anti-symmetric matrix:

$$F^{\mu\nu} = \begin{pmatrix} 0 & -E_x & -E_y & -E_z \\ E_x & 0 & -B_z & B_y \\ E_y & B_z & 0 & -B_x \\ E_z & -B_y & B_x & 0 \end{pmatrix} \quad (49)$$

Defining some dummy variables to make equations look cleaner:

$$\begin{aligned} \lambda_1 &= \sqrt{\beta_x^2 + \beta_y^2 + \beta_z^2} \\ \lambda_2 &= \beta_x \delta\beta_x + \beta_y \delta\beta_y + \beta_z \delta\beta_z \\ \lambda_3 &= \beta_y^2 \delta\beta_x - \beta_x \beta_y \delta\beta_y + \beta_z (\beta_z \delta\beta_x - \beta_x \delta\beta_z) \\ \lambda_4 &= \beta_x^2 \delta\beta_y - \beta_x \beta_y \delta\beta_x + \beta_z (\beta_z \delta\beta_y - \beta_y \delta\beta_z) \\ \lambda_5 &= \beta_x^2 \delta\beta_z - \beta_x \beta_z \delta\beta_x + \beta_y (\beta_y \delta\beta_z - \beta_z \delta\beta_y) \\ \lambda_6 &= \beta_x \delta\beta_y - \beta_y \delta\beta_x \\ \lambda_7 &= \beta_y \delta\beta_z - \beta_z \delta\beta_y \\ \lambda_8 &= \beta_z \delta\beta_x - \beta_x \delta\beta_z \\ \eta_1 &= \sqrt{\beta_x^2 + \beta_y^2} \\ \eta_2 &= \sqrt{\beta_y^2 + \beta_z^2} \\ \eta_3 &= \sqrt{\beta_x^2 + \beta_z^2} \end{aligned}$$

The detailed expressions of the electromagnetic fields (to the first order in $\delta\beta$) can be written as:

A. Longitudinal-Transverse ℓt -Frame

1. Direct Boosted Frame ($\vec{\beta} + \delta\vec{\beta}$)

$$(\mathbf{F}'')^{10} = \frac{1}{\lambda_1} \left[\beta_x E_x + \beta_y E_y + \beta_z E_z - \lambda_3 E_x \gamma^2 - \lambda_4 E_y \gamma^2 - \lambda_5 E_z \gamma^2 + B_z \lambda_6 \gamma + B_y \lambda_8 \gamma + B_x \lambda_7 \gamma + \frac{\gamma(\gamma-1)\eta_2^2 \delta\beta_x E_x}{\lambda_1^2} \right. \\ \left. + \frac{\gamma(\gamma-1)\eta_3^2 \delta\beta_y E_y}{\lambda_1^2} + \frac{\gamma(\gamma-1)\eta_1^2 \delta\beta_z E_z}{\lambda_1^2} - \frac{\gamma(\gamma-1)\beta_x \beta_y \delta\beta_y E_x}{\lambda_1^2} - \frac{\gamma(\gamma-1)\beta_x \beta_z \delta\beta_z E_x}{\lambda_1^2} - \frac{\gamma(\gamma-1)\beta_x \beta_y \delta\beta_x E_y}{\lambda_1^2} \right. \\ \left. - \frac{\gamma(\gamma-1)\beta_y \beta_z \delta\beta_z E_y}{\lambda_1^2} - \frac{\gamma(\gamma-1)\beta_x \beta_z \delta\beta_x E_z}{\lambda_1^2} - \frac{\gamma(\gamma-1)\beta_y \beta_z \delta\beta_y E_z}{\lambda_1^2} \right]$$

$$(\mathbf{F}'')^{20} = -\gamma B_z \eta_1 + \frac{\gamma B_x \beta_x \beta_z}{\eta_1} + \frac{\gamma B_y \beta_y \beta_z}{\eta_1} - \frac{\gamma E_x \beta_y}{\eta_1} + \frac{\gamma \beta_x E_y}{\eta_1} - \frac{\gamma^3 B_z \beta_x \eta_1 \delta\beta_x}{\lambda_1^2} + \frac{\gamma^2 \delta\beta_x \beta_y \beta_z E_z}{\eta_1} - \frac{\gamma^3 B_z \beta_y \eta_1 \delta\beta_y}{\lambda_1^2} \\ + \frac{\gamma(\gamma^2-1) B_x \beta_x^2 \beta_z \delta\beta_x}{\eta_1 \lambda_1^2} + \frac{\gamma(\gamma^2-1) B_y \beta_x \delta\beta_x \beta_y \beta_z}{\eta_1 \lambda_1^2} - \frac{\gamma B_z \beta_x \delta\beta_x \beta_z^2}{\eta_1 \lambda_1^2} - \frac{\gamma B_z \beta_y \delta\beta_y \beta_z^2}{\eta_1 \lambda_1^2} + \frac{\gamma B_x \beta_x \eta_1 \delta\beta_z}{\lambda_1^2} \\ + \frac{\gamma(\gamma^2-1) B_y \beta_y^2 \delta\beta_y \beta_z}{\eta_1 \lambda_1^2} + \frac{\gamma(\gamma^2-1) B_x \beta_x \beta_y \delta\beta_y \beta_z}{\eta_1 \lambda_1^2} - \frac{\gamma(\gamma^2-1) B_z \beta_z \eta_1 \delta\beta_z}{\lambda_1^2} - \frac{(\gamma-1)\gamma^2 \beta_x \delta\beta_x E_x \beta_y}{\eta_1} \\ + \frac{\gamma^3 B_x \beta_x \beta_z^2 \delta\beta_z}{\eta_1 \lambda_1^2} + \frac{\gamma^3 B_y \beta_y \beta_z^2 \delta\beta_z}{\eta_1 \lambda_1^2} + \frac{\gamma B_y \beta_y \eta_1 \delta\beta_z}{\lambda_1^2} - \frac{\gamma^3 E_x \beta_y^2 \delta\beta_y}{\eta_1} - \frac{\gamma^2 \beta_x^2 E_x \delta\beta_y}{\eta_1} - \frac{\gamma^3 E_x \beta_y \beta_z \delta\beta_z}{\eta_1} + \frac{\gamma^3 \beta_x^2 \delta\beta_x E_y}{\eta_1} \\ + \frac{(\gamma-1)\gamma \beta_x^2 E_x \delta\beta_y}{\eta_1 \lambda_1^2} - \frac{(\gamma-1)\gamma \beta_x \delta\beta_x E_x \beta_y}{\eta_1 \lambda_1^2} + \frac{(\gamma-1)\gamma^2 \beta_x \beta_y \delta\beta_y E_y}{\eta_1} - \frac{(\gamma-1)\gamma \delta\beta_x \beta_y^2 E_y}{\eta_1 \lambda_1^2} + \frac{\gamma^2 \delta\beta_x \beta_y^2 E_y}{\eta_1} \\ + \frac{\gamma^3 \beta_x E_y \beta_z \delta\beta_z}{\eta_1} - \frac{\gamma^2 \beta_x \delta\beta_y \beta_z E_z}{\eta_1} + \frac{(\gamma-1)\gamma \beta_x \delta\beta_y \beta_z E_z}{\eta_1 \lambda_1^2} - \frac{(\gamma-1)\gamma \delta\beta_x \beta_y \beta_z E_z}{\eta_1 \lambda_1^2} + \frac{(\gamma-1)\gamma \beta_x \beta_y \delta\beta_y E_y}{\eta_1 \lambda_1^2}$$

$$(\mathbf{F}'')^{30} = \frac{\gamma B_y \beta_x \lambda_1}{\eta_1} - \frac{\gamma B_x \beta_y \lambda_1}{\eta_1} - \frac{\gamma \beta_x E_x \beta_z}{\eta_1 \lambda_1} - \frac{\gamma \beta_y E_y \beta_z}{\eta_1 \lambda_1} + \frac{\gamma E_z \eta_1}{\lambda_1} + \frac{\gamma^3 B_y \beta_x^2 \delta\beta_x}{\eta_1 \lambda_1} + \frac{\gamma B_y \delta\beta_x \beta_y^2}{\eta_1 \lambda_1} - \frac{\gamma B_x \beta_x^2 \delta\beta_y}{\eta_1 \lambda_1} \\ - \frac{\gamma^3 B_x \beta_y^2 \delta\beta_y}{\eta_1 \lambda_1} - \frac{\gamma B_z \beta_z \lambda_6}{\eta_1 \lambda_1} + \frac{\gamma(\gamma^2-1) B_y \beta_x \beta_y \delta\beta_y}{\eta_1 \lambda_1} - \frac{\gamma(\gamma^2-1) B_x \beta_x \delta\beta_x \beta_y}{\eta_1 \lambda_1} - \frac{(\gamma-1)\gamma \beta_x^2 \delta\beta_x E_x \beta_z}{\eta_1 \lambda_1^3} \\ + \frac{\gamma^3 B_y \beta_x \beta_z \delta\beta_z}{\eta_1 \lambda_1} - \frac{\gamma^3 B_x \beta_y \beta_z \delta\beta_z}{\eta_1 \lambda_1} - \frac{\gamma^2 \beta_x E_x \delta\beta_z \eta_1}{\lambda_1} - \frac{(\gamma-1)\gamma^2 \beta_x^2 \delta\beta_x E_x \beta_z}{\eta_1 \lambda_1} - \frac{(\gamma-1)\gamma^2 \beta_x E_x \beta_y \delta\beta_y \beta_z}{\eta_1 \lambda_1} \\ + \frac{(\gamma-1)\gamma \beta_x E_x \delta\beta_z \eta_1}{\lambda_1^3} - \frac{(\gamma-1)\gamma \beta_x E_x \beta_y \delta\beta_y \beta_z}{\eta_1 \lambda_1^3} - \frac{(\gamma-1)\gamma^2 \beta_x \delta\beta_x \beta_y E_y \beta_z}{\eta_1 \lambda_1} - \frac{(\gamma-1)\gamma^2 \beta_y^2 \delta\beta_y E_y \beta_z}{\eta_1 \lambda_1} \\ - \frac{\gamma^3 \beta_x E_x \beta_z^2 \delta\beta_z}{\eta_1 \lambda_1} - \frac{\gamma^2 \beta_y E_y \delta\beta_z \eta_1}{\lambda_1} + \frac{(\gamma-1)\gamma \beta_y E_y \lambda_5}{\eta_1 \lambda_1^3} - \frac{\gamma^3 \beta_y E_y \beta_z^2 \delta\beta_z}{\eta_1 \lambda_1} + \frac{(\gamma-1)\gamma \beta_z \delta\beta_z E_z \eta_1}{\lambda_1^3} \\ + \frac{\gamma^3 \beta_y \delta\beta_y E_z \eta_1}{\lambda_1} + \frac{\gamma^3 \beta_x \delta\beta_x E_z \eta_1}{\lambda_1} + \frac{\gamma^2 \beta_x \delta\beta_x \beta_z^2 E_z}{\eta_1 \lambda_1} - \frac{(\gamma-1)\gamma \beta_y \delta\beta_y \beta_z^2 E_z}{\eta_1 \lambda_1^3} + \frac{(\gamma-1)\gamma^2 \beta_z \delta\beta_z E_z \eta_1^3}{\lambda_1^3} \\ + \frac{\gamma^2 \beta_y \delta\beta_y \beta_z^2 E_z}{\eta_1 \lambda_1} + \frac{(\gamma-1)\gamma^2 \beta_z^3 \delta\beta_z E_z \eta_1}{\lambda_1^3} - \frac{(\gamma-1)\gamma \beta_x \delta\beta_x \beta_z^2 E_z}{\eta_1 \lambda_1^3}$$

$$(\mathbf{F}'')^{32} = \frac{1}{\lambda_1} \left[B_x \beta_x + B_y \beta_y + B_z \beta_z - \gamma E_x \lambda_7 - \gamma E_y \lambda_8 - \gamma E_z \lambda_6 - \frac{(\gamma-1)B_z \lambda_5}{\lambda_1^2} - \frac{(\gamma-1)B_y \lambda_4}{\lambda_1^2} - \frac{(\gamma-1)B_x \lambda_3}{\lambda_1^2} \right]$$

$$\begin{aligned}
(\mathbf{F}'')^{13} = & -\frac{\gamma B_x \beta_y}{\eta_1} + \frac{\gamma B_y \beta_x}{\eta_1} - \frac{\gamma \beta_x E_x \beta_z}{\eta_1} - \frac{\gamma \beta_y E_y \beta_z}{\eta_1} + \gamma E_z \eta_1 - \frac{\gamma^3 B_x \beta_x \delta \beta_x \beta_y}{\eta_1} - \frac{\gamma^3 B_x \beta_y^2 \delta \beta_y}{\eta_1} - \frac{\gamma^3 B_x \beta_y \beta_z \delta \beta_z}{\eta_1} \\
& + \frac{\gamma^3 B_y \beta_x \beta_y \delta \beta_y}{\eta_1} + \frac{\gamma^3 B_y \beta_x^2 \delta \beta_x}{\eta_1} + \frac{\gamma^3 B_y \beta_x \beta_z \delta \beta_z}{\eta_1} - \frac{\gamma^3 \beta_x E_x \beta_z^2 \delta \beta_z}{\eta_1 \lambda_1^2} + \frac{(\gamma-1) B_x \beta_x \delta \beta_x \beta_y}{\eta_1 \lambda_1^2} - \frac{(\gamma-1) B_x \beta_x^2 \delta \beta_y}{\eta_1 \lambda_1^2} \\
& + \frac{(\gamma-1) B_y \delta \beta_x \beta_y^2}{\eta_1 \lambda_1^2} + \frac{(\gamma-1) B_z \delta \beta_x \beta_y \beta_z}{\eta_1 \lambda_1^2} - \frac{(\gamma-1) B_y \beta_x \beta_y \delta \beta_y}{\eta_1 \lambda_1^2} - \frac{(\gamma-1) B_z \beta_x \delta \beta_y \beta_z}{\eta_1 \lambda_1^2} - \frac{(\gamma^2-1) \gamma \beta_x^2 \delta \beta_x E_x \beta_z}{\eta_1 \lambda_1^2} \\
& - \frac{(\gamma^2-1) \gamma \beta_x E_x \beta_y \delta \beta_y \beta_z}{\eta_1 \lambda_1^2} - \frac{\gamma \beta_x E_x \delta \beta_z \eta_1}{\lambda_1^2} - \frac{\gamma (\gamma^2-1) \beta_y^2 \delta \beta_y E_y \beta_z}{\eta_1 \lambda_1^2} - \frac{\gamma (\gamma^2-1) \beta_x \delta \beta_x \beta_y E_y \beta_z}{\eta_1 \lambda_1^2} - \frac{\gamma \beta_y E_y \delta \beta_z \eta_1}{\lambda_1^2} \\
& - \frac{\gamma^3 \beta_y E_y \beta_z^2 \delta \beta_z}{\eta_1 \lambda_1^2} + \frac{\gamma^3 \beta_y \delta \beta_y E_z \eta_1}{\lambda_1^2} + \frac{\gamma^3 \beta_x \delta \beta_x E_z \eta_1}{\lambda_1^2} + \frac{\gamma \beta_x \delta \beta_x \beta_z^2 E_z}{\eta_1 \lambda_1^2} + \frac{\gamma (\gamma^2-1) \beta_z \delta \beta_z E_z \eta_1}{\lambda_1^2} + \frac{\gamma \beta_y \delta \beta_y \beta_z^2 E_z}{\eta_1 \lambda_1^2} \\
(\mathbf{F}'')^{12} = & \frac{\gamma B_z \eta_1}{\lambda_1} - \frac{\gamma B_x \beta_x \beta_z}{\eta_1 \lambda_1} - \frac{\gamma B_y \beta_y \beta_z}{\eta_1 \lambda_1} + \frac{\gamma E_x \beta_y \lambda_1}{\eta_1} - \frac{\gamma \beta_x E_y \lambda_1}{\eta_1} + \frac{(\gamma-1) B_x \beta_x^2 \delta \beta_x \beta_z}{\eta_1 \lambda_1^3} - \frac{\gamma^3 B_x \beta_x^2 \delta \beta_x \beta_z}{\eta_1 \lambda_1} - \frac{\gamma \delta \beta_x \beta_y^2 E_y}{\eta_1 \lambda_1} \\
& - \frac{\gamma^3 B_y \beta_x \delta \beta_x \beta_y \beta_z}{\eta_1 \lambda_1} + \frac{\gamma^3 B_z \beta_x \delta \beta_x \eta_1}{\lambda_1} + \frac{\gamma^3 B_z \beta_y \delta \beta_y \eta_1}{\lambda_1} - \frac{\gamma^3 B_x \beta_x \beta_y \delta \beta_y \beta_z}{\eta_1 \lambda_1} - \frac{\gamma^3 B_y \beta_y^2 \delta \beta_y \beta_z}{\eta_1 \lambda_1} - \frac{\gamma^3 B_x \beta_x \beta_z^2 \delta \beta_z}{\eta_1 \lambda_1} \\
& + \frac{(\gamma-1) B_z \beta_x \delta \beta_x \beta_z^2}{\eta_1 \lambda_1^3} + \frac{(\gamma-1) B_y \beta_x \delta \beta_x \beta_y \beta_z}{\eta_1 \lambda_1^3} + \frac{(\gamma-1) B_x \beta_x \beta_y \delta \beta_y \beta_z}{\eta_1 \lambda_1^3} + \frac{(\gamma-1) B_y \beta_y^2 \delta \beta_y \beta_z}{\eta_1 \lambda_1^3} + \frac{(\gamma-1) B_z \beta_y \delta \beta_y \beta_z^2}{\eta_1 \lambda_1^3} \\
& - \frac{(\gamma-1) B_x \beta_x \delta \beta_z \eta_1}{\lambda_1^3} - \frac{(\gamma-1) B_y \beta_y \delta \beta_z \eta_1}{\lambda_1^3} - \frac{(\gamma-1) B_z \beta_z \delta \beta_z \eta_1}{\lambda_1^3} + \frac{\gamma (\gamma^2-1) \beta_x \delta \beta_x E_x \beta_y}{\eta_1 \lambda_1} - \frac{(\gamma^2-1) \gamma \beta_x \beta_y \delta \beta_y E_y}{\eta_1 \lambda_1} \\
& - \frac{\gamma^3 B_y \beta_y \beta_z^2 \delta \beta_z}{\eta_1 \lambda_1} + \frac{\gamma^3 B_z \beta_z \delta \beta_z \eta_1}{\lambda_1} + \frac{\gamma^3 E_x \beta_y^2 \delta \beta_y}{\eta_1 \lambda_1} + \frac{\gamma^3 E_x \beta_y \beta_z \delta \beta_z}{\eta_1 \lambda_1} + \frac{\gamma \beta_x^2 E_x \delta \beta_y}{\eta_1 \lambda_1} - \frac{\gamma^3 \beta_x^2 \delta \beta_x E_y}{\eta_1 \lambda_1} - \frac{\gamma^3 \beta_x E_y \beta_z \delta \beta_z}{\eta_1 \lambda_1} \\
& - \frac{\gamma \delta \beta_x \beta_y \beta_z E_z}{\eta_1 \lambda_1} + \frac{\gamma \beta_x \delta \beta_y \beta_z E_z}{\eta_1 \lambda_1}
\end{aligned}$$

2. Successively Boosted Frame $\vec{\beta}$ and $\Delta \vec{\beta}$

$$\begin{aligned}
(\mathbf{F}''')^{10} = & \frac{\beta_x E_x}{\lambda_1} + \frac{\beta_y E_y}{\lambda_1} + \frac{\beta_z E_z}{\lambda_1} + \frac{\gamma^2 B_z \lambda_6}{\lambda_1} + \frac{\gamma^2 B_y \lambda_8}{\lambda_1} + \frac{\gamma^2 B_x \lambda_7}{\lambda_1} + \frac{\gamma^2 \beta_x E_x \beta_y \delta \beta_y}{\lambda_1} + \frac{\gamma^2 \beta_x E_x \beta_z \delta \beta_z}{\lambda_1} - \frac{\gamma^2 \delta \beta_x E_x \eta_2^2}{\lambda_1} \\
& + \frac{\gamma^2 \beta_y E_y \beta_z \delta \beta_z}{\lambda_1} - \frac{\gamma^2 \delta \beta_y E_y \eta_3^2}{\lambda_1} + \frac{\gamma^2 \beta_x \delta \beta_x \beta_y E_y}{\lambda_1} + \frac{\gamma^2 \beta_y \delta \beta_y \beta_z E_z}{\lambda_1} + \frac{\gamma^2 \beta_x \delta \beta_x \beta_z E_z}{\lambda_1} - \frac{\gamma^2 \delta \beta_z E_z \eta_1^2}{\lambda_1} \\
(\mathbf{F}''')^{20} = & \frac{2\gamma B_y \beta_y \beta_z}{\eta_1} - \gamma B_z \eta_1 - \frac{\gamma E_x \beta_y}{\eta_1} + \frac{\gamma \beta_x E_y}{\eta_1} - \frac{\gamma^3 B_z \eta_1 \lambda_2}{\lambda_1^2} + \frac{\gamma B_z \beta_z \lambda_5}{\eta_1 \lambda_1^2} - \frac{\gamma^3 E_x \beta_y \lambda_2}{\eta_1} + \frac{\gamma^3 \beta_x E_y \lambda_2}{\eta_1} + \frac{2\gamma B_y \beta_y \delta \beta_z \eta_1}{\lambda_1^2} \\
& + \frac{2\gamma (\gamma^2-1) B_y \beta_y^2 \delta \beta_y \beta_z}{\eta_1 \lambda_1^2} + \frac{2\gamma (\gamma^2-1) B_y \beta_x \delta \beta_x \beta_y \beta_z}{\eta_1 \lambda_1^2} + \frac{2\gamma^3 B_y \beta_y \beta_z^2 \delta \beta_z}{\eta_1 \lambda_1^2} \\
(\mathbf{F}''')^{30} = & \frac{\gamma B_y \beta_x \lambda_1}{\eta_1} - \frac{\gamma B_x \beta_y \lambda_1}{\eta_1} - \frac{\gamma \beta_x E_x \beta_z}{\eta_1 \lambda_1} - \frac{\gamma \beta_y E_y \beta_z}{\eta_1 \lambda_1} + \frac{\gamma E_z \eta_1}{\lambda_1} - \frac{\gamma B_x \beta_x \lambda_6}{\eta_1 \lambda_1} - \frac{\gamma B_y \beta_y \lambda_6}{\eta_1 \lambda_1} - \frac{\gamma B_z \beta_z \lambda_6}{\eta_1 \lambda_1} + \frac{\gamma^3 B_y \beta_x \lambda_2}{\eta_1 \lambda_1} \\
& - \frac{\gamma^3 B_x \beta_y \lambda_2}{\eta_1 \lambda_1} - \frac{\gamma^3 \beta_x E_x \beta_z \lambda_2}{\eta_1 \lambda_1} - \frac{\gamma^3 \beta_y E_y \beta_z \lambda_2}{\eta_1 \lambda_1} + \frac{\gamma^3 E_z \eta_1 \lambda_2}{\lambda_1} \\
(\mathbf{F}''')^{32} = & \frac{1}{\lambda_1} [B_x \beta_x + B_y \beta_y + B_z \beta_z - \gamma^2 E_x \lambda_7 - \gamma^2 E_y \lambda_8 - \gamma^2 E_z \lambda_6 + \gamma^2 B_z \beta_x \delta \beta_x \beta_z + \gamma^2 B_x \beta_x \beta_y \delta \beta_y + \gamma^2 B_z \beta_y \delta \beta_y \beta_z \\
& - \gamma^2 B_x \delta \beta_x \eta_2^2 - \gamma^2 B_y \delta \beta_y \eta_3^2 - \gamma^2 B_z \delta \beta_z \eta_1^2 + \gamma^2 B_y \beta_y \beta_z \delta \beta_z + \gamma^2 B_x \beta_x \beta_z \delta \beta_z + \gamma^2 B_y \beta_x \delta \beta_x \beta_y]
\end{aligned}$$

$$(\mathbf{F}''')^{13} = -\frac{\gamma B_x \beta_y}{\eta_1} + \frac{\gamma B_y \beta_x}{\eta_1} - \frac{\gamma \beta_x E_x \beta_z}{\eta_1} - \frac{\gamma \beta_y E_y \beta_z}{\eta_1} + \gamma E_z \eta_1 - \frac{\gamma^3 B_x \beta_y \lambda_2}{\eta_1} + \frac{\gamma^3 B_y \beta_x \lambda_2}{\eta_1} - \frac{\gamma^3 \beta_x E_x \beta_z \lambda_2}{\eta_1 \lambda_1^2} - \frac{\gamma^3 \beta_y E_y \beta_z \lambda_2}{\eta_1 \lambda_1^2} \\ - \frac{\gamma \beta_x E_x \lambda_5}{\eta_1 \lambda_1^2} - \frac{\gamma \beta_y E_y \lambda_5}{\eta_1 \lambda_1^2} + \frac{\gamma^3 E_z \eta_1 \lambda_2}{\lambda_1^2} - \frac{\gamma \beta_z E_z \lambda_5}{\eta_1 \lambda_1^2}$$

$$(\mathbf{F}''')^{21} = \frac{\gamma B_z \eta_1}{\lambda_1} - \frac{\gamma B_x \beta_x \beta_z}{\eta_1 \lambda_1} - \frac{\gamma B_y \beta_y \beta_z}{\eta_1 \lambda_1} + \frac{\gamma E_x \beta_y \lambda_1}{\eta_1} - \frac{\gamma \beta_x E_y \lambda_1}{\eta_1} - \frac{\gamma^3 B_x \beta_x \beta_z \lambda_2}{\eta_1 \lambda_1} - \frac{\gamma^3 B_y \beta_y \beta_z \lambda_2}{\eta_1 \lambda_1} + \frac{\gamma^3 B_z \eta_1 \lambda_2}{\lambda_1} + \frac{\gamma^3 E_x \beta_y \lambda_2}{\eta_1 \lambda_1} \\ + \frac{\gamma \beta_x E_x \lambda_6}{\eta_1 \lambda_1} - \frac{\gamma^3 \beta_x E_y \lambda_2}{\eta_1 \lambda_1} + \frac{\gamma \beta_y E_y \lambda_6}{\eta_1 \lambda_1} + \frac{\gamma \beta_z E_z \lambda_6}{\eta_1 \lambda_1}$$

B. Laboratory xy -Frame

1. Direct Boosted Frame ($\vec{\beta} + \delta\vec{\beta}$)

$$(\mathbf{F}'')^{10} = \gamma B_z \beta_y - \gamma B_y \beta_z - \gamma^2 \beta_x^2 E_x + \frac{1}{\lambda_1^2} [\gamma E_x (\gamma \beta_x^2 + \beta_y^2 + \beta_z^2) - (\gamma - 1) \beta_x \beta_y E_y - (\gamma - 1) \beta_x \beta_z E_z - \gamma^3 B_y \beta_z \lambda_2 + \gamma^3 B_z \beta_y \lambda_2 \\ + \gamma B_z \lambda_4 + \gamma^3 \beta_x \delta \beta_x E_x \eta_2^2 + \gamma^3 E_x \beta_y \delta \beta_y \eta_2^2 + \gamma^3 E_x \beta_z \delta \beta_z \eta_2^2 - \gamma^3 \beta_x \beta_y \delta \beta_y \beta_z E_z - \gamma^3 \beta_x \beta_z \delta \beta_z E_z - \gamma^3 \beta_x^2 \delta \beta_x \beta_y E_y \\ - \gamma B_y \lambda_5 - \gamma^3 \beta_x \beta_y^2 \delta \beta_y E_y - \gamma^3 \beta_x \beta_y E_y \beta_z \delta \beta_z - \gamma^3 \beta_x^2 \delta \beta_x \beta_z E_z + \frac{2(\gamma - 1) \beta_x^2 E_x \beta_y \delta \beta_y}{\lambda_1^2} + \frac{2(\gamma - 1) \beta_x^2 E_x \beta_z \delta \beta_z}{\lambda_1^2} \\ - \frac{(\gamma - 1) \delta \beta_x \beta_y E_y (-\beta_x^2 + \beta_y^2 + \beta_z^2)}{\lambda_1^2} + \frac{2(\gamma - 1) \beta_x \beta_y E_y \beta_z \delta \beta_z}{\lambda_1^2} - \frac{(\gamma - 1) \beta_x \delta \beta_y E_y (\beta_x^2 - \beta_y^2 + \beta_z^2)}{\lambda_1^2} + \frac{2(\gamma - 1) \beta_x \beta_y \delta \beta_y \beta_z E_z}{\lambda_1^2} \\ - \frac{(\gamma - 1) \delta \beta_x \beta_z E_z (-\beta_x^2 + \beta_y^2 + \beta_z^2)}{\lambda_1^2} - \frac{(\gamma - 1) \beta_x \delta \beta_z E_z (\beta_x^2 + \beta_y^2 - \beta_z^2)}{\lambda_1^2} - \frac{2(\gamma - 1) \beta_x \delta \beta_x E_x \eta_2^2}{\lambda_1^2}]$$

$$(\mathbf{F}'')^{20} = \gamma B_x \beta_z - \gamma B_z \beta_x - \gamma^2 \beta_x E_x \beta_y - \gamma^2 \beta_y^2 E_y - \gamma^2 \beta_y \beta_z E_z + \frac{1}{\lambda_1^2} [\gamma^2 \beta_y^2 E_y + \gamma E_y \eta_3^2 + \gamma^3 \beta_x \delta \beta_x E_y \eta_3^2 + \gamma^3 \beta_y \delta \beta_y E_y \eta_3^2 \\ + (\gamma - 1) \gamma \beta_x E_x \beta_y + (\gamma - 1) \gamma \beta_y \beta_z E_z - \gamma^3 B_z \beta_x^2 \delta \beta_x + (\gamma^2 - 1) \gamma B_x \beta_x \delta \beta_x \beta_z - (\gamma^2 - 1) \gamma B_z \beta_x \beta_y \delta \beta_y - \gamma B_z \delta \beta_x \eta_2^2 \\ + \gamma^3 B_x \beta_z^2 \delta \beta_z - (\gamma^2 - 1) \gamma B_z \beta_x \beta_z \delta \beta_z + \gamma (\gamma^2 - 1) B_x \beta_y \delta \beta_y \beta_z + \gamma B_x \delta \beta_z \eta_1^2 - \gamma^3 \beta_x E_x \beta_y \beta_z \delta \beta_z + \gamma^3 E_y \beta_z \delta \beta_z \eta_3^2 \\ - \gamma^3 \beta_x^2 \delta \beta_x E_x \beta_y - \gamma^3 \beta_x E_x \beta_y^2 \delta \beta_y - \gamma^3 \beta_x \delta \beta_x \beta_y \beta_z E_z - \gamma^3 \beta_y^2 \delta \beta_y \beta_z E_z - \gamma^3 \beta_y \beta_z^2 \delta \beta_z E_z - \frac{(\gamma - 1) \beta_y \delta \beta_z E_z (\beta_x^2 + \beta_y^2 - \beta_z^2)}{\lambda_1^2} \\ - \frac{(\gamma - 1) \delta \beta_x E_x \beta_y (-\beta_x^2 + \beta_y^2 + \beta_z^2)}{\lambda_1^2} - \frac{(\gamma - 1) \beta_x E_x \delta \beta_y (\beta_x^2 - \beta_y^2 + \beta_z^2)}{\lambda_1^2} + \frac{2(\gamma - 1) \beta_x \delta \beta_x \beta_y^2 E_y}{\lambda_1^2} - \frac{2(\gamma - 1) \beta_y \delta \beta_y E_y \eta_3^2}{\lambda_1^2} \\ + \frac{2(\gamma - 1) \beta_y^2 E_y \beta_z \delta \beta_z}{\lambda_1^2} + \frac{2(\gamma - 1) \beta_x \delta \beta_x \beta_y \beta_z E_z}{\lambda_1^2} - \frac{(\gamma - 1) \delta \beta_y \beta_z E_z (\beta_x^2 - \beta_y^2 + \beta_z^2)}{\lambda_1^2} + \frac{2(\gamma - 1) \beta_x E_x \beta_y \beta_z \delta \beta_z}{\lambda_1^2}]$$

$$\begin{aligned}
(\mathbf{F}'')^{30} = & \gamma B_y \beta_x - \gamma B_x \beta_y - \gamma^2 \beta_z^2 E_z + \frac{1}{\lambda_1^2} \left[\gamma^3 B_y \beta_x^2 \delta \beta_x - (\gamma - 1) \beta_x E_x \beta_z - (\gamma - 1) \beta_y E_y \beta_z + \gamma E_z (\beta_x^2 + \beta_y^2 + \gamma \beta_z^2) \right. \\
& + \gamma^3 B_y \beta_x \beta_y \delta \beta_y - \gamma^3 B_x \beta_y^2 \delta \beta_y - (\gamma^2 - 1) \gamma B_x \beta_x \delta \beta_x \beta_y + \gamma B_y \delta \beta_x \eta_2^2 - \gamma B_y \beta_x \beta_y \delta \beta_y + \gamma^3 B_y \beta_x \beta_z \delta \beta_z \\
& - \gamma^3 B_x \beta_y \beta_z \delta \beta_z + \gamma B_x \beta_y \beta_z \delta \beta_z - \gamma B_x \delta \beta_y \eta_3^2 - \gamma B_y \beta_x \beta_z \delta \beta_z - \gamma^3 \beta_x^2 \delta \beta_x E_x \beta_z - \gamma^3 \beta_x E_x \beta_y \delta \beta_y \beta_z - \gamma^3 \beta_y E_y \beta_z^2 \delta \beta_z \\
& - \gamma^3 \beta_x E_x \beta_z^2 \delta \beta_z - \gamma^3 \beta_x \delta \beta_x \beta_y E_y \beta_z - \gamma^3 \beta_y^2 \delta \beta_y E_y \beta_z + \gamma^3 \beta_x \delta \beta_x E_z \eta_1^2 + \gamma^3 \beta_y \delta \beta_y E_z \eta_1^2 + \gamma^3 \beta_z \delta \beta_z E_z \eta_1^2 \\
& - \frac{(\gamma - 1) \delta \beta_x E_x \beta_z (\beta_x^2 + \beta_y^2 + \beta_z^2)}{\lambda_1^2} + \frac{2(\gamma - 1) \beta_x E_x \beta_y \delta \beta_y \beta_z}{\lambda_1^2} - \frac{(\gamma - 1) \beta_x E_x \delta \beta_z (\beta_x^2 + \beta_y^2 - \beta_z^2)}{\lambda_1^2} + \frac{2(\gamma - 1) \beta_x \delta \beta_x \beta_y E_y \beta_z}{\lambda_1^2} \\
& - \frac{(\gamma - 1) \delta \beta_y E_y \beta_z (\beta_x^2 - \beta_y^2 + \beta_z^2)}{\lambda_1^2} - \frac{(\gamma - 1) \beta_y E_y \delta \beta_z (\beta_x^2 + \beta_y^2 - \beta_z^2)}{\lambda_1^2} + \frac{2(\gamma - 1) \beta_x \delta \beta_x \beta_z^2 E_z}{\lambda_1^2} + \frac{2(\gamma - 1) \beta_y \delta \beta_y \beta_z^2 E_z}{\lambda_1^2} \\
& \left. - \frac{2(\gamma - 1) \beta_z \delta \beta_z E_z \eta_1^2}{\lambda_1^2} \right]
\end{aligned}$$

$$\begin{aligned}
(\mathbf{F}'')^{32} = & \gamma E_y \beta_z - \gamma \beta_y E_z + \frac{1}{\lambda_1^2} \left[B_x \beta_x^2 + \gamma B_x \eta_2^2 - (\gamma - 1) B_y \beta_x \beta_y - (\gamma - 1) B_z \beta_x \beta_z - \gamma^3 B_y \beta_x^2 \delta \beta_x \beta_y - \gamma^3 B_z \beta_x^2 \delta \beta_x \beta_z \right. \\
& + \gamma^3 B_x \beta_x \delta \beta_x \eta_2^2 + \gamma^3 B_x \beta_y \delta \beta_y \eta_2^2 - \gamma^3 B_y \beta_x \beta_y^2 \delta \beta_y - \gamma^3 B_z \beta_x \beta_y \delta \beta_y \beta_z + \gamma^3 B_x \beta_z \delta \beta_z \eta_2^2 - \gamma^3 B_z \beta_x \beta_z^2 \delta \beta_z \\
& - \gamma^3 B_y \beta_x \beta_y \beta_z \delta \beta_z - \gamma \delta \beta_y E_z \eta_3^2 + \gamma^3 E_y \beta_z^2 \delta \beta_z + (\gamma^2 - 1) \gamma \beta_y \delta \beta_y E_y \beta_z + \gamma (\gamma^2 - 1) \beta_x \delta \beta_x E_y \beta_z + \gamma E_y \delta \beta_z \eta_1^2 \\
& - \gamma^3 \beta_y^2 \delta \beta_y E_z - (\gamma^2 - 1) \gamma \beta_x \delta \beta_x \beta_y E_z - (\gamma^2 - 1) \gamma \beta_y \beta_z \delta \beta_z E_z - \frac{2(\gamma - 1) B_x \beta_x \delta \beta_x \eta_2^2}{\lambda_1^2} + \frac{2(\gamma - 1) B_x \beta_x^2 \beta_z \delta \beta_z}{\lambda_1^2} \\
& + \frac{2(\gamma - 1) B_y \beta_x \beta_y \beta_z \delta \beta_z}{\lambda_1^2} + \frac{2(\gamma - 1) B_x \beta_x^2 \beta_y \delta \beta_y}{\lambda_1^2} - \frac{(\gamma - 1) B_z \delta \beta_x \beta_z (-\beta_x^2 + \beta_y^2 + \beta_z^2)}{\lambda_1^2} + \frac{2(\gamma - 1) B_z \beta_x \beta_y \delta \beta_y \beta_z}{\lambda_1^2} \\
& \left. - \frac{(\gamma - 1) B_y \beta_x \delta \beta_y (\beta_x^2 - \beta_y^2 + \beta_z^2)}{\lambda_1^2} - \frac{(\gamma - 1) B_y \delta \beta_x \beta_y (-\beta_x^2 + \beta_y^2 + \beta_z^2)}{\lambda_1^2} - \frac{(\gamma - 1) B_z \beta_x \delta \beta_z (\beta_x^2 + \beta_y^2 - \beta_z^2)}{\lambda_1^2} \right]
\end{aligned}$$

$$\begin{aligned}
(\mathbf{F}'')^{13} = & -\gamma E_x \beta_z + \gamma \beta_x E_z + \frac{1}{\lambda_1^2} \left[B_y \beta_y^2 + \gamma B_y \eta_3^2 - (\gamma - 1) B_z \beta_y \beta_z - (\gamma - 1) B_x \beta_x \beta_y - \gamma^3 B_x \beta_x^2 \delta \beta_x \beta_y - \gamma^3 B_z \beta_y^2 \delta \beta_y \beta_z \right. \\
& - \gamma^3 B_x \beta_x \beta_y^2 \delta \beta_y - \gamma^3 B_x \beta_x \beta_y \beta_z \delta \beta_z + \gamma^3 \beta_x \beta_z \delta \beta_z E_z + \gamma^3 \beta_x^2 \delta \beta_x E_z + \gamma \delta \beta_x E_z \eta_2^2 - \gamma \beta_x \beta_y \delta \beta_y E_z - \gamma \beta_x \beta_z \delta \beta_z E_z \\
& - \gamma^3 E_x \beta_z^2 \delta \beta_z - (\gamma^2 - 1) \gamma \beta_x \delta \beta_x E_x \beta_z - (\gamma^2 - 1) \gamma E_x \beta_y \delta \beta_y \beta_z - \gamma E_x \delta \beta_z \eta_1^2 + \gamma^3 \beta_x \beta_y \delta \beta_y E_z - \gamma^3 B_z \beta_y \beta_z^2 \delta \beta_z \\
& + \gamma^3 B_y \beta_x \delta \beta_x \eta_3^2 + \gamma^3 B_y \beta_z \delta \beta_z \eta_3^2 + \gamma^3 B_y \beta_y \delta \beta_y \eta_3^2 - \gamma^3 B_z \beta_x \delta \beta_x \beta_y \beta_z + \frac{2(\gamma - 1) B_y \beta_x \delta \beta_x \beta_y^2}{\lambda_1^2} - \frac{2(\gamma - 1) B_y \beta_y \delta \beta_y \eta_3^2}{\lambda_1^2} \\
& + \frac{2(\gamma - 1) B_y \beta_y^2 \beta_z \delta \beta_z}{\lambda_1^2} + \frac{2(\gamma - 1) B_z \beta_x \delta \beta_x \beta_y \beta_z}{\lambda_1^2} - \frac{(\gamma - 1) B_z \delta \beta_y \beta_z (\beta_x^2 - \beta_y^2 + \beta_z^2)}{\lambda_1^2} - \frac{(\gamma - 1) B_z \beta_y \delta \beta_z (\beta_x^2 + \beta_y^2 - \beta_z^2)}{\lambda_1^2} \\
& \left. + \frac{2(\gamma - 1) B_x \beta_x \beta_y \beta_z \delta \beta_z}{\lambda_1^2} - \frac{(\gamma - 1) B_x \delta \beta_x \beta_y (-\beta_x^2 + \beta_y^2 + \beta_z^2)}{\lambda_1^2} - \frac{(\gamma - 1) B_x \beta_x \delta \beta_y (\beta_x^2 - \beta_y^2 + \beta_z^2)}{\lambda_1^2} \right]
\end{aligned}$$

$$\begin{aligned}
(\mathbf{F}'')^{21} = & \gamma E_x \beta_y - \gamma \beta_x E_y + \frac{1}{\lambda_1^2} \left[B_z \beta_z^2 + \gamma B_z \eta_1^2 - (\gamma - 1) B_x \beta_x \beta_z - (\gamma - 1) B_y \beta_y \beta_z + \gamma^3 B_z \beta_x \delta \beta_x \eta_1^2 - \gamma^3 B_x \beta_x^2 \delta \beta_x \beta_z \right. \\
& - \gamma^3 \beta_x^2 \delta \beta_x E_y - \gamma^3 \beta_x \beta_y \delta \beta_y E_y - \gamma^3 \beta_x E_y \beta_z \delta \beta_z + \gamma \beta_x \beta_y \delta \beta_y E_y + \gamma \beta_x E_y \beta_z \delta \beta_z - \gamma \delta \beta_x E_y \eta_2^2 + \gamma E_x \delta \beta_y \eta_3^2 \\
& + (\gamma^2 - 1) \gamma E_x \beta_y \beta_z \delta \beta_z + \gamma (\gamma^2 - 1) \beta_x \delta \beta_x E_x \beta_y - \gamma^3 B_y \beta_x \delta \beta_x \beta_y \beta_z + \gamma^3 B_z \beta_y \delta \beta_y \eta_1^2 - \gamma^3 B_y \beta_y^2 \delta \beta_y \beta_z \\
& - \gamma^3 B_x \beta_x \beta_y \delta \beta_y \beta_z + \gamma^3 B_z \beta_z \delta \beta_z \eta_1^2 - \gamma^3 B_x \beta_x \beta_z^2 \delta \beta_z - \gamma^3 B_y \beta_y \beta_z^2 \delta \beta_z + \gamma^3 E_x \beta_y^2 \delta \beta_y + \frac{2(\gamma - 1) B_z \beta_y \delta \beta_y \beta_z}{\lambda_1^2} \\
& + \frac{2(\gamma - 1) B_y \beta_x \delta \beta_x \beta_y \beta_z}{\lambda_1^2} + \frac{2(\gamma - 1) B_z \beta_x \delta \beta_x \beta_z^2}{\lambda_1^2} - \frac{(\gamma - 1) B_y \delta \beta_y \beta_z (\beta_x^2 - \beta_y^2 + \beta_z^2)}{\lambda_1^2} - \frac{2(\gamma - 1) B_z \beta_z \delta \beta_z \eta_1^2}{\lambda_1^2} \\
& - \frac{(\gamma - 1) B_x \beta_x \delta \beta_z (\beta_x^2 + \beta_y^2 - \beta_z^2)}{\lambda_1^2} - \frac{(\gamma - 1) B_x \delta \beta_x \beta_z (-\beta_x^2 + \beta_y^2 + \beta_z^2)}{\lambda_1^2} + \frac{2(\gamma - 1) B_x \beta_x \beta_y \delta \beta_y \beta_z}{\lambda_1^2} \\
& \left. - \frac{(\gamma - 1) B_y \beta_y \delta \beta_z (\beta_x^2 + \beta_y^2 - \beta_z^2)}{\lambda_1^2} \right]
\end{aligned}$$

2. Successively Boosted Frame $\vec{\beta}$ and $\Delta\vec{\beta}$

$$\begin{aligned}
(\mathbf{F}''')^{10} = & \gamma B_z \beta_y - \gamma B_y \beta_z - \gamma^2 \beta_x^2 E_x - \gamma^2 \beta_x \beta_z E_z - \gamma^2 \beta_x \beta_y E_y + \frac{1}{\lambda_1^2} \left[\gamma^2 \beta_x^2 E_x + \gamma E_x \eta_2^2 + \gamma^2 \beta_x \beta_y E_y - \gamma \beta_x \beta_y E_y - \gamma^2 \beta_x E_z \lambda_5 \right. \\
& + \gamma^2 \beta_x \beta_z E_z - \gamma \beta_x \beta_z E_z + \gamma^2 B_y \beta_x \delta \beta_x \beta_z - \gamma^2 B_z \beta_x \delta \beta_x \beta_y + \gamma B_y \beta_y \delta \beta_y \beta_z - \gamma B_z \beta_y \beta_z \delta \beta_z - (\gamma - 1) \gamma B_x \beta_x \delta \beta_y \beta_z \\
& - \gamma^3 B_y \beta_z \lambda_2 + \gamma B_z \delta \beta_y (\gamma \beta_x^2 + \beta_z^2) - \gamma B_y \delta \beta_z (\gamma \beta_x^2 + \beta_y^2) - \gamma^2 \beta_x E_x \lambda_3 - \gamma^3 \beta_x \beta_y E_y \lambda_2 + (\gamma - 1) \gamma B_x \beta_x \beta_y \delta \beta_z \\
& \left. - \gamma^2 \beta_x E_y \lambda_4 - \gamma^3 \beta_x \beta_z E_z \lambda_2 + \gamma^3 E_x \eta_2^2 \lambda_2 + \gamma^3 B_z \beta_y \lambda_2 \right]
\end{aligned}$$

$$\begin{aligned}
(\mathbf{F}''')^{20} = & \gamma B_x \beta_z - \gamma B_z \beta_x - \gamma^2 \beta_x E_x \beta_y - \gamma^2 \beta_y^2 E_y - \gamma^2 \beta_y \beta_z E_z + \frac{1}{\lambda_1^2} \left[\gamma^3 B_x \beta_y \delta \beta_y \beta_z (\gamma - 1) \gamma \beta_x E_x \beta_y + (\gamma - 1) \gamma \beta_y \beta_z E_z \right. \\
& + \gamma^3 B_x \beta_x \delta \beta_x \beta_z - \gamma^3 B_z \beta_x^2 \delta \beta_x + \gamma^2 B_z \beta_x \beta_y \delta \beta_y + (\gamma - 1) \gamma B_y \delta \beta_x \beta_y \beta_z - \gamma B_x \beta_x \delta \beta_x \beta_z + \gamma^2 \beta_x \delta \beta_x \beta_y^2 E_y - \gamma^3 \beta_y^2 \delta \beta_y \beta_z E_z \\
& + \gamma E_y (\beta_x^2 + \gamma \beta_y^2 + \beta_z^2) - \gamma^3 B_z \beta_x \beta_y \delta \beta_y - \gamma^2 B_x \beta_y \delta \beta_y \beta_z + \gamma B_x \delta \beta_z (\beta_x^2 + \gamma \beta_y^2) + \gamma B_z \beta_x \beta_z \delta \beta_z - (\gamma - 1) \gamma B_y \beta_x \beta_y \delta \beta_z \\
& - \gamma^3 B_z \beta_x \beta_z \delta \beta_z + \gamma^3 B_x \beta_z^2 \delta \beta_z - \gamma^3 \beta_x^2 \delta \beta_x E_x \beta_y - \gamma^3 \beta_x E_x \beta_y^2 \delta \beta_y + \gamma^2 \beta_x E_x \beta_y^2 \delta \beta_y - \gamma^2 \delta \beta_x E_x \beta_y \eta_2^2 + \gamma^2 \beta_x E_x \beta_y \beta_z \delta \beta_z \\
& - \gamma^3 \beta_x E_x \beta_y \beta_z \delta \beta_z + \gamma^3 \beta_x \delta \beta_x E_y \eta_3^2 - \gamma^2 \beta_y \delta \beta_y E_y \eta_3^2 + \gamma^3 \beta_y \delta \beta_y E_y \eta_3^2 + \gamma^2 \beta_y^2 E_y \beta_z \delta \beta_z + \gamma^3 E_y \beta_z \delta \beta_z \eta_3^2 - \gamma^2 \beta_y \delta \beta_z E_z \eta_1^2 \\
& \left. - \gamma^3 \beta_x \delta \beta_x \beta_y \beta_z E_z - \gamma^3 \beta_y \beta_z^2 \delta \beta_z E_z + \gamma^2 \beta_y^2 \delta \beta_y \beta_z E_z + \gamma^2 \beta_x \delta \beta_x \beta_y \beta_z E_z - \gamma B_z \delta \beta_x (\gamma \beta_y^2 + \beta_z^2) \right]
\end{aligned}$$

$$\begin{aligned}
(\mathbf{F}''')^{30} = & \gamma B_y \beta_x - \gamma B_x \beta_y - \gamma^2 \beta_x E_x \beta_z - \gamma^2 \beta_y E_y \beta_z - \gamma^2 \beta_z^2 E_z + \frac{1}{\lambda_1^2} \left[\gamma^3 B_y \beta_x^2 \delta \beta_x (\gamma - 1) \gamma \beta_x E_x \beta_z + (\gamma - 1) \gamma \beta_y E_y \beta_z \right. \\
& + \gamma E_z (\beta_x^2 + \beta_y^2 + \gamma \beta_z^2) - \gamma^3 B_x \beta_x \delta \beta_x \beta_y + \gamma B_y \delta \beta_x (\beta_y^2 + \gamma \beta_z^2) + \gamma B_x \beta_x \delta \beta_x \beta_y - (\gamma - 1) \gamma B_z \delta \beta_x \beta_y \beta_z - \gamma B_y \beta_x \beta_y \delta \beta_y \\
& + \gamma^3 B_y \beta_x \beta_y \delta \beta_y - \gamma^2 B_y \beta_x \beta_z \delta \beta_z + (\gamma - 1) \gamma B_z \beta_x \delta \beta_y \beta_z - \gamma B_x \delta \beta_y (\beta_x^2 + \gamma \beta_z^2) - \gamma^3 B_x \beta_y \beta_z \delta \beta_z + \gamma^3 B_y \beta_x \beta_z \delta \beta_z \\
& + \gamma^2 B_x \beta_y \beta_z \delta \beta_z - \gamma^3 \beta_x^2 \delta \beta_x E_x \beta_z - \gamma^3 \beta_x E_x \beta_y \delta \beta_y \beta_z + \gamma^2 \beta_x E_x \beta_y \delta \beta_y \beta_z - \gamma^2 \delta \beta_x E_x \beta_z \eta_2^2 + \gamma^2 \beta_x E_x \beta_z^2 \delta \beta_z \\
& - \gamma^3 \beta_x E_x \beta_z^2 \delta \beta_z - \gamma^3 \beta_x \delta \beta_x \beta_y E_y \beta_z - 2\gamma^3 \beta_y^2 \delta \beta_y E_y \beta_z - 2\gamma^2 \delta \beta_y E_y \beta_z \eta_3^2 + \gamma^2 \beta_x \delta \beta_x \beta_y E_y \beta_z + \gamma^2 \beta_y E_y \beta_z^2 \delta \beta_z \\
& - \gamma^3 \beta_y E_y \beta_z^2 \delta \beta_z + \gamma^3 \beta_y \delta \beta_y E_z \eta_1^2 + \gamma^3 \beta_z \delta \beta_z E_z \eta_1^2 + \gamma^3 \beta_x \delta \beta_x E_z \eta_1^2 + \gamma^2 \beta_x \delta \beta_x \beta_z^2 E_z - \gamma^2 \beta_z \delta \beta_z E_z \eta_1^2 - \gamma^3 B_x \beta_y^2 \delta \beta_y \\
& \left. + \gamma^2 \beta_y \delta \beta_y \beta_z^2 E_z \right]
\end{aligned}$$

$$\begin{aligned}
(\mathbf{F}''')^{32} = & \gamma E_y \beta_z - \gamma \beta_y E_z + \gamma^3 \beta_y \delta \beta_y E_y \beta_z - \gamma^3 \beta_y^2 E_y \delta \beta_z + \gamma^3 \delta \beta_y \beta_z^2 E_z - \gamma^3 \beta_y \beta_z \delta \beta_z E_z + \frac{1}{\lambda_1^2} \left[-\gamma^2 B_y \beta_x \lambda_4 + \gamma^3 B_x \eta_2^2 \lambda_2 \right. \\
& - (\gamma - 1) B_z \beta_x \beta_z + B_x (\beta_x^2 + \gamma (\beta_y^2 + \beta_z^2)) + (\gamma - 1) \gamma \beta_x E_x \delta \beta_y \beta_z - (\gamma - 1) \gamma \beta_x E_x \beta_y \delta \beta_z - \gamma^2 B_z \beta_x \lambda_5 - \gamma^3 B_z \beta_x \beta_z \lambda_2 \\
& + \gamma^2 E_y \delta \beta_z (\beta_x^2 + \gamma (\beta_y^2 + \beta_z^2)) - \gamma^2 \delta \beta_y E_z (\beta_x^2 + \gamma (\beta_y^2 + \beta_z^2)) (\gamma - 1) \gamma^2 \beta_x \delta \beta_x E_y \beta_z - (\gamma - 1) B_y \beta_x \beta_y - \gamma^3 B_y \beta_x \beta_y \lambda_2 \\
& \left. - \gamma^2 B_x \beta_x \lambda_3 - (\gamma - 1) \gamma^2 \beta_x \delta \beta_x \beta_y E_z \right]
\end{aligned}$$

$$\begin{aligned}
(\mathbf{F}''')^{13} &= \gamma\beta_x E_z - \gamma E_x \beta_z - \gamma^3 \beta_x \delta\beta_x E_x \beta_z + \gamma^3 \beta_x^2 E_x \delta\beta_z + \gamma^3 \beta_x \beta_z \delta\beta_z E_z + \frac{1}{\lambda_1^2} [\gamma^3 B_y \eta_3^2 \lambda_2 - \gamma^2 B_x \beta_y \lambda_3 - \gamma^3 B_x \beta_x \beta_y \lambda_2 \\
&\quad + \gamma \delta\beta_x \beta_z^2 E_z - (\gamma - 1) B_x \beta_x \beta_y - (\gamma - 1) B_z \beta_y \beta_z - \gamma^2 B_y \beta_y \lambda_4 - \gamma^2 \delta\beta_x \beta_y E_y \beta_z - \gamma^2 B_z \beta_y \lambda_5 - \gamma \beta_x \beta_y E_y \delta\beta_z \\
&\quad - \gamma^3 B_z \beta_y \beta_z \lambda_2 - \gamma^2 E_x \beta_y^2 \delta\beta_z - (\gamma - 1) \gamma^2 E_x \beta_y \delta\beta_y \beta_z - \gamma^3 E_x \delta\beta_z \eta_3^2 + \gamma^2 \beta_x \beta_y E_y \delta\beta_z + \gamma^3 \beta_x^2 \delta\beta_x E_z + \gamma^2 \delta\beta_x \beta_y^2 E_z \\
&\quad + \gamma \delta\beta_x \beta_y E_y \beta_z + (\gamma - 1) \gamma^2 \beta_x \beta_y \delta\beta_y E_z + B_y (\gamma \beta_x^2 + \beta_y^2 + \gamma \beta_z^2)] \\
(\mathbf{F}''')^{21} &= \gamma^3 \beta_x \delta\beta_x E_x \beta_y - \gamma^3 \beta_x^2 E_x \delta\beta_y + \gamma E_x \beta_y + \gamma^3 \delta\beta_x \beta_y^2 E_y - \gamma \beta_x E_y - \gamma^3 \beta_x \beta_y \delta\beta_y E_y + \gamma^3 \delta\beta_x \beta_y \beta_z E_z - \gamma^3 \beta_x \delta\beta_y \beta_z E_z \\
&\quad + \frac{1}{\lambda_1^2} [\gamma^3 B_z \eta_1^2 \lambda_2 - (\gamma - 1) B_x \beta_x \beta_z - (\gamma - 1) B_y \beta_y \beta_z + B_z (\gamma \beta_x^2 + \gamma \beta_y^2 + \beta_z^2) - \gamma^3 B_x \beta_x \beta_z \lambda_2 - \gamma^3 B_y \beta_y \beta_z \lambda_2 \\
&\quad + \gamma^3 E_x \delta\beta_y \eta_1^2 - \gamma^3 \delta\beta_x E_y \eta_1^2 - \gamma^2 B_x \beta_z \lambda_3 - \gamma^2 B_y \beta_z \lambda_4 - \gamma^2 B_z \beta_z \lambda_5 + (\gamma - 1) \gamma^2 E_x \beta_y \beta_z \delta\beta_z - (\gamma - 1) \gamma^2 \beta_x E_y \beta_z \delta\beta_z \\
&\quad + (\gamma - 1) \gamma^2 \beta_z E_z \lambda_6 + \gamma^2 E_x \delta\beta_y \beta_z^2 - \gamma^2 \delta\beta_x E_y \beta_z^2]
\end{aligned}$$

C. Comparison with the References

As mentioned in the Introduction, this work is inspired by Ungar et al. [9–14, 16] so it is natural to compare our approach with Ungar to see if we share the same overall features. To check that we will work for a 2-dimensional case for simplicity by letting $\beta_y = \beta_z = \delta\beta_z = 0$ in Eq. (37) which will give [6]:

$$A(\Delta\vec{\beta}) = \begin{pmatrix} 1 & -\gamma^2 \delta\beta_x & -\gamma \delta\beta_y & 0 \\ -\gamma^2 \delta\beta_x & 1 & 0 & 0 \\ -\gamma \delta\beta_y & 0 & 1 & 0 \\ 0 & 0 & 0 & 1 \end{pmatrix} \quad (50)$$

From $A(\Delta\vec{\beta})$, the relativistic velocity composition can be easily extracted:

$$\Delta\vec{\beta} = \gamma^2 \delta\beta_x \hat{x} + \gamma \delta\beta_y \hat{y} \quad (51)$$

Now for the three different inertial frames discussed in the Introduction Σ , Σ' and Σ'' , we have

Relative velocity of Σ' with respect to Σ : $\vec{\beta}$
Relative velocity of Σ'' with respect to Σ' : $\Delta\vec{\beta}$

We can now use the relativistic velocity composition rule mentioned in Eq. (8) to calculate the relative velocity of Σ'' with respect to Σ [9–14, 16] by defining:

$$\begin{aligned}
\vec{u} &= \vec{\beta} = \beta \hat{x} \\
\vec{v} &= \Delta\vec{\beta} = \gamma^2 \delta\beta_x \hat{x} + \gamma \delta\beta_y \hat{y} \\
\gamma_u &= \gamma \\
\gamma_v &\approx 1
\end{aligned}$$

After plugging in the values and simplifying, we get:

$$\begin{aligned}
(\vec{u} \oplus \vec{v})_x &= \frac{\beta + \gamma^2 \delta\beta_x}{1 + \gamma^2 \beta \delta\beta_x} \\
(\vec{u} \oplus \vec{v})_y &= \frac{\gamma \delta\beta_y}{1 + \gamma^2 \beta \delta\beta_x} \\
\gamma_{\vec{u} \oplus \vec{v}} &\approx \gamma(1 + \gamma^2 \beta \delta\beta_x) \quad (52)
\end{aligned}$$

Constructing the boost matrix from the above equation:

$$A(\vec{\beta} + \delta\vec{\beta}) = \begin{pmatrix} \gamma + \gamma^3 \beta \delta\beta_x & -(\gamma \beta + \gamma^3 \delta\beta_x) & -\gamma \delta\beta_y & 0 \\ -(\gamma \beta + \gamma^3 \delta\beta_x) & \gamma + \gamma^3 \beta \delta\beta_x & (\gamma - 1) \frac{\delta\beta_y}{\beta} & 0 \\ -\gamma \delta\beta_y & (\gamma - 1) \frac{\delta\beta_y}{\beta} & 1 & 0 \\ 0 & 0 & 0 & 1 \end{pmatrix}$$

We can compare this boost matrix with Eq. (39) and notice that they are completely identical. Therefore our

approach gives the identical final result as discussed in [9–14, 16].

[1] L. H. Thomas, *Nature*, **117**, 514(1926); *Phil. Mag.* **3**, 1 (1927).

[2] J. D. Jackson, *Classical Electrodynamics*, Third Edition,

- Sec-11.3 (John Wiley & Sons, Inc., 1999)
- [3] J. D. Jackson, *Classical Electrodynamics*, Third Edition, Sec-11.4 (John Wiley & Sons, Inc., 1999)
- [4] J. D. Jackson, *Classical Electrodynamics*, Third Edition, Sec-11.6 (John Wiley & Sons, Inc., 1999)
- [5] J. D. Jackson, *Classical Electrodynamics*, Third Edition, Sec-11.7 (John Wiley & Sons, Inc., 1999)
- [6] J. D. Jackson, *Classical Electrodynamics*, Third Edition, Sec-11.8 (John Wiley & Sons, Inc., 1999)
- [7] J. D. Jackson, *Classical Electrodynamics*, Third Edition, Sec-11.9 (John Wiley & Sons, Inc., 1999)
- [8] J. D. Jackson, *Classical Electrodynamics*, Third Edition, Sec-11.10 (John Wiley & Sons, Inc., 1999)
- [9] Ungar, A. A. *Found Phys Lett* 1, **57**, (1988). <https://doi.org/10.1007/BF00661317>
- [10] Ungar, A. A. *Found Phys* (1997) **27**: 881. <https://doi.org/10.1007/BF02550347>
- [11] Ungar, A. A. *Found Phys* (1989) **19**: 1385. <https://doi.org/10.1007/BF00732759>
- [12] Ungar, A. A. *Found Phys* (1991) **21**: 569. <https://doi.org/10.1007/BF00733259>
- [13] Ungar, A. A. *Results. Math.* (1989) **16**: 168. <https://doi.org/10.1007/BF03322653>
- [14] Ungar, A. A. *Am. J. Phys.* **59**, 824 (1991). <https://doi.org/10.1119/1.16730>
- [15] Ungar, A. A. *Found Phys Lett* (1989) **2**: 199. <https://doi.org/10.1007/BF00696113>
- [16] Ungar, A. A. *Found Phys* (2000) **30**: 331. <https://doi.org/10.1023/A:1003653302643>
- [17] S. K. Lamoreaux and R. Golub, *Phys. Rev. A* **71**, 032104 (2005).
- [18] A. L. Barabanov, R. Golub, and S. K. Lamoreaux, *Phys. Rev. A* **74**, 052115 (2006).
- [19] G. Pignol, M. Guigue, A. Petukhov, and R. Golub, *Phys. Rev. A* **92**, 053407 (2015).