

A Fast, Parallel Algorithm for Distant-dependent Calculation of Crystal Properties

Matthew Stein*

Southern Methodist University

3215 Daniel Ave.

Dallas, Texas, 75205, USA

(Dated: June 7, 2021)

A fast, parallel algorithm for distant-dependent calculation and simulation of crystal properties is presented along with speedup results and methods of application. An illustrative example is used to compute the Lennard-Jones lattice constants up to 32 significant figures for $4 \leq p \leq 30$ in the simple cubic, face-centered cubic, body-centered cubic, hexagonal-close-pack, and diamond lattices. In most cases, the known precision of these constants is more than doubled, and in some cases, corrected from previously published figures. The tools and strategies to make this computation possible are detailed along with application to other potentials, including those that model defects.

Keywords: Parallel Algorithms, Crystal Potential Energy, Lattice Constants, Computational Approaches, Classical Potentials

I. INTRODUCTION

Calculations of crystal potentials or force interactions, whether through molecular dynamics or classical potentials, will rely on functions of distances between many atoms. In either case, computational complexity and time will limit the precision with which values are calculated. Even in the case of classical potentials, which are less computationally intense, crystal simulations and calculations are usually limited to the millions of atoms, with determined values often having fewer significant figures than a single-precision float.

Classical potential fitting has also become more complex in attempts to adapt a single model to a greater number of situations. The Lennard-Jones potential [1] is simple and widely used for its computational speed, but much more accurate models exist. The Buckingham potential [2] expanded on the Lennard-Jones potential, replacing the Pauli repulsive term with an exponential function but at computational cost. The Stillinger-Weber potential [3] (hereafter SW potential) was proposed as a further improvement, now taking into account not just distance between atoms but also the angles of their bonds in a new 3-body term.

Improvements on the classical potentials have thus progressed for decades [4–7], with attempts to find a potential model that works not only with perfect crystals, but those with point defects, plane defects, and more. A fitted formula in one situation (temperature, lattice, atomic composition) often does not suitably agree with experimental values from another. As such, the potentials grow ever more complex, and determining parameters comes at greater cost, but the objective of a transferable model remains a priority.

Rather than limiting calculations to a small number of atoms (and thus limited precision), or expanding compute time (which schedules and resources may not permit), a faster optimized algorithm could be used to

achieve better and/or less costly results. Additionally, potentials with arbitrary cut-off values (often used to shorten compute time) can be relaxed for better fitting of other parameters and more realistic simulation. An adaptive algorithm would also ideally be suited for studies of non-ideal lattices with defects, vacancies or other imperfections.

The inclusion of contributions from further atoms or those with defect locations should also come with questions about the precision of the calculation. For example, a single interstitial sufficiently far away from a reference atom may not affect the total potential energy, but a plane defect at the same distance may have significant contributions when all atoms across the plane are considered. It may be useful to use very high-precision variables in computation, further advancing the need for a faster algorithm.

II. COMPUTATIONAL APPROACH

Potential and force calculations in a crystal depend on distances between pairs of atoms. Any summation over lattice points will first require the calculation of the distance between these atoms r_{ij} , and then apply some function $f(r_{ij})$ to that distance. The return value is included in the total sum. The algorithms presented here can be used for any such distance-dependent function.

For illustrative purposes, the Lennard-Jones potential will be used as an example of the computational power of this new algorithm. Further extensions and adaptations of the same algorithm to other functions and potentials are discussed in Section III.

The author would like to note there are many common techniques to optimize algorithms, especially nested loops, such as avoiding the repetitive calculation of the same value. Likewise there are algorithms to avoid round-off error such as the Kahan summation algorithm [8]. These common tools are omitted from the algorithms presented here to more clearly show the logic structure, and to more clearly demonstrate what new methods are

* mstein@smu.edu

applied.

A. An Illustrative Example

The Lennard-Jones potential [1] is a simple but widely-used potential energy formula. The total potential energy of a crystal with N atoms is described by the sum of Equation (1) between all pairs of atoms. The constant parameters σ and ϵ are determined from experimental measurements, and d_j is the distance from a fixed reference atom to any other atom j as a multiple of the nearest-neighbor distance.

$$U_{tot} = 2N\epsilon \left[\sum_{j=1}^{\infty} \left(\frac{\sigma}{d_j} \right)^{12} - \sum_{j=1}^{\infty} \left(\frac{\sigma}{d_j} \right)^6 \right] \quad (1)$$

To simplify calculations, it is useful to separate the d_j terms and examine them independently:

$$L_p \equiv \sum_{j=1}^{\infty} \left(\frac{1}{d_j} \right)^p \quad (2)$$

It is seen that Equation (1) can be determined by first calculating these lattice constants L_p for $p = 6$ and $p = 12$. The $p = 6$ term represents the attractive van der Waals force, whereas the Pauli exclusion principle is responsible for the repulsive $p = 12$ term. The choice of $p = 12$ is not fully motivated from first principles, so it is useful to compute a range of p values. For $p < 4$, the series does not converge [9], and for $p > 30$, the series is seen to converge to the coordination number of the lattice. While any real value of p could be computed, this example uses integer values for comparison to other published results which also examine integer values of p [9, 10].

To achieve a useful value of the lattice constants L_p in Equation (2), the series need only converge to the precision required. The double-precision float has ~ 15 decimal digits, and is now a very fast variable to use with most modern compilers. Results have been published for the simple cubic (SC), face-centered cubic (FCC), body-centered cubic (BCC), hexagonal-close-pack (HCP) lattices with up to 15 decimal digits [9], but not every term published has actually converged to the precision given, especially for $p < 12$. The diamond (DIA) lattice has been published up to 9 decimal digits [10], roughly the precision of a 32-bit single-precision float. To fully demonstrate the power of the algorithms in this work, the Portable, Extensible Toolkit for Scientific Computation (PETSc) [11] was used to implement 128-bit floats to push the precision to 32 decimal digits.

B. Brute Force Method

Consider a SC lattice whose side length is D , and whose unit cell has a side length of 1 in arbitrary units.

To calculate a distance-dependent function $f(r_{ij})$ over all lattice sites (Equation 2), one can set up three nested **for**-loops to cover a 3-dimensional grid. Each integer value of the respective loop variables (X, Y, Z) represent the coordinates of a particular atom, and sweeping from $-(D/2)$ to $(D/2)$ in all three loops covers all $(D+1)^3$ atoms in the cube.

The distance d_j from the origin to any other atom j is, of course, $\sqrt{X^2 + Y^2 + Z^2}$ so the program structure then is:

Algorithm 1 Brute Force Method

```

 $L_p = 0$ 
for  $X \leftarrow -(D/2)$  to  $(D/2)$  do
  for  $Y \leftarrow -(D/2)$  to  $(D/2)$  do
    for  $Z \leftarrow -(D/2)$  to  $(D/2)$  do
      if  $X = 0$  and  $Y = 0$  and  $Z = 0$  then
        Next
      else
         $L_p += \frac{1}{(X^2 + Y^2 + Z^2)^{p/2}}$ 
return  $L_p$ 

```

The **if**-statement is present to avoid the $\frac{1}{0}$ term (at the origin) which would otherwise set L_p equal to infinity or NaN . At this point, knowing that there will be $(D+1)^3$ **if**-statements checked in every run of Algorithm 1, it is worth finding how many terms will be necessary for this sum to converge.

C. The Convergent Series

Depending on implementation of 128-bit floats [12], these variables yield ~ 32 decimal digits for each term. Finding where Equation (2) converges then requires additional terms to be equal to or less than 10^{-33} (in arbitrary units). Finding the coordinates of where $L_{p_j} = 10^{-33}$ yields little benefit, however, as that is only the value of one such term, and there may be many such terms at that distance.


For example, say $L_{p_j} = \frac{1}{(X_j^2 + Y_j^2 + Z_j^2)^{p/2}} = 10^{-33}$ for atom j at (X_j, Y_j, Z_j) , and say $Y_j = Z_j = 0$ for simplicity. In the brute force method described above, the algorithm will still be computing approximately R^2 more terms for the face at $X_j = R$. Moreover, there will be six such faces to add to the total sum. Higher distances decrease the value of each L_{p_j} term, but there are more terms to the total sum at some fixed R , slowing down the convergence of the series with increasing distance (Figure 1). One can calculate the total amount added to L_p from adding one layer at a fixed R distance, showing the slowness of convergence. For L_6 , the total value added from one layer at distance R goes as $1/R^4$ (Equation 3). This is determined by integrating Equation (2) with respect to Y and Z for $p = 6$ and $X = R$. That result is multiplied by 6 for symmetry.

While an exact result requires the actual summation in Equation (2), this result is useful for determining how many terms are required for convergence to a particular precision.

$$Sum_{p,face@R} \propto \frac{1}{R^{(p-2)}}$$

$$Sum_{6,face@R} = 6 \times \frac{2 + 15\sqrt{2}\text{ArcCot}\sqrt{2}}{12R^4} \approx \frac{7.52815}{R^4} \quad (3)$$

FIG. 1. Average value of terms added to L_6 from the face at some fixed R versus the distance and number of terms added to L_6 at that face.



The convergence of Equation (2) is much faster for higher values of p (Figure 2) but presents a significant computational challenge for low p . Converging to any desired precision at low p will then require finding fast algorithms that will capitalize on efficiency, parallelism, and any inherent symmetries in the crystal lattice.

D. Finding Speedup

1. Avoiding Unnecessary Operations

In the simple case of Algorithm 1, the $(D+1)^3$ **if** statements can be avoided by structuring the program to calculate different regions of the same cube, none of which contain the $(0,0,0)$ position (Figure 3). There are now six regions to consider: two rectangular parallelepipeds, two planes, and two lines. The loops for these regions are executed in serial (Algorithm 2).

2. Parallelization

Since each individual L_{p_i} value is independent of every other L_{p_j} , Algorithm 2 is an excellent candidate for

FIG. 2. Average value of terms added to L_p across the face at some fixed R versus the distance R . One can draw a horizontal line across the graph at the desired precision on the vertical axis. Where that line intersects each p function will be approximately the distance required to converge the sum at that precision.





FIG. 3. The six volumes to loop over, automatically avoiding the unit cell at the origin. The red regions indicate the 2-dimensional face planes, and the green regions are the 1-dimensional axes.



parallelization via MPI [13]. The parallelization of these nested **for**-loops, however, requires the following careful prescription such that each thread does approximately the same amount of work, and the entire 3-dimensional grid of lattice points is covered. For $NumProcs$ threads, one cannot simply set thread number $MyID$ to cover

Algorithm 2 Broken Down into Six Separate Regions

```

 $L_p = 0$ 
// Cube Volumes
for  $X \leftarrow -(D/2)$  to  $(D/2)$  do
  for  $Y \leftarrow -(D/2)$  to  $(D/2)$  do
    for  $Z \leftarrow -(D/2)$  to  $-1$  do
       $L_p += \frac{1}{(X^2+Y^2+Z^2)^{p/2}}$ 
  for  $X \leftarrow -(D/2)$  to  $(D/2)$  do
    for  $Y \leftarrow -(D/2)$  to  $(D/2)$  do
      for  $Z \leftarrow 1$  to  $(D/2)$  do
         $L_p += \frac{1}{(X^2+Y^2+Z^2)^{p/2}}$ 
// Faces @  $Z = 0$ 
for  $X \leftarrow -(D/2)$  to  $(D/2)$  do
  for  $Y \leftarrow -(D/2)$  to  $-1$  do
     $L_p += \frac{1}{(X^2+Y^2)^{p/2}}$ 
for  $X \leftarrow -(D/2)$  to  $(D/2)$  do
  for  $Y \leftarrow 1$  to  $(D/2)$  do
     $L_p += \frac{1}{(X^2+Y^2)^{p/2}}$ 
// Axes @  $Y = 0$  and  $Z = 0$ 
for  $X \leftarrow -(D/2)$  to  $-1$  do
   $L_p += \frac{1}{X^p}$ 
for  $X \leftarrow 1$  to  $(D/2)$  do
   $L_p += \frac{1}{X^p}$ 
return  $L_p$ 

```

a range of $(D/NumProcs)$ in $(X/Y/Z)$ as can be trivially done in the case of a 1-dimensional array. Instead, the original cube from Algorithm 1 is broken down into $NumProcs$ inter-penetrating cubes with a different basis. This allows every thread to compute $\frac{(D+1)^3}{NumProcs}$ elements of L_p , the results of which can be combined at the end of the algorithm. The integer basis of each new lattice is computed as follows:

$$Basis = \text{Floor}(\sqrt[3]{NumProcs}) \quad (4)$$

The initial (X, Y, Z) position of each thread is:

$$\begin{aligned}
X_i &= (MyID \% Basis) + (D/2) \\
Y_i &= (\text{Floor} \left[\frac{MyID}{Basis} \right] \% Basis) + (D/2) \\
Z_i &= (\text{Floor} \left[\frac{MyID}{Basis^2} \right] \% Basis) + (D/2)
\end{aligned} \quad (5)$$

Fortunately, only one thread (hereafter the *origin thread*) will pass through the $(0, 0, 0)$ position. All other threads can execute a fast triple-nested **for**-loop (Algorithm 3, Figure 4), and the origin thread will execute a slightly modified version of Algorithm 2. The origin thread is identified as:

$$k = (D/2) \% Basis$$

$$OriginThreadNum = k * Basis^2 + k * Basis + k$$


Algorithm 3 Invoked in Parallel
(Threads other than origin thread)

```

 $L_p = 0$ 
... set  $X_i, Y_i, Z_i...$ 
for  $X \leftarrow X_i$  to  $-(D/2)$  in steps of  $-Basis$  do
  for  $Y \leftarrow Y_i$  to  $-(D/2)$  in steps of  $-Basis$  do
    for  $Z \leftarrow Z_i$  to  $-(D/2)$  in steps of  $-Basis$  do
       $L_p += \frac{1}{(X^2+Y^2+Z^2)^{p/2}}$ 
... MPI summation ...
return  $L_{p,total}$ 

```

FIG. 4. Example of atom sites in the SC lattice looped over by a single thread (blue) for an 8-thread invocation of Algorithm 3. The remaining green sites are divided among the other seven threads. In a real lattice, the spheres should be uniform and expanded to fill the maximum volume possible, but are shown with different sizes here for clarity.



A simple MPI summation is performed at the end of the program, and the result is returned.


One caveat with this prescription is that it requires $NumProcs$ to have an integer cube root. On small clusters with a limited number of threads, this can prevent the full utilization of this method, but even consumer processors are widely available in 8-core (or more) configurations which is the minimum required. More flexible methods not requiring a cubic number of threads are possible, but come at a performance cost. The cluster used for this example (Southern Methodist University's ManeFrame) has over 1,100 CPU nodes available, each with eight cores, making over 8,800 simultaneous threads

possible, erasing the need for programming more flexible methods.

3. Exploiting Symmetry


In the case of the SC lattice, the calculation of L_p can be shortened by considering that the cube is made of eight identical, smaller pieces corresponding to each octant. Therefore a speedup of almost eightfold can be found by calculating only one of these octants and multiplying the end result. However, the algorithmic range of each octant is not as obvious as it seems. There are unit cells along the planes between octants whose atoms need to have their contributions handled carefully as some of the atoms sit astride different octants (Figure 5), and likewise for cells along the axes. For unit cells immediately adjacent other octants, consider these as being in separate volumes called the axis or face volumes (for cells touching the axes or faces between octants, respectively) as in Figure 6). The remaining cells are considered to be in one of eight cubic volumes spanning the rest of each octant. Therefore, in the entire lattice, there are eight cubic volumes, 12 face volumes, and six half-axis volumes. In the case of the SC lattice, one need only calculate the sum of a single cubic volume L_{cube} , a single face L_{face} , and a single half-axis L_{axis} to determine L_p (Equation 6).

FIG. 5. SC unit cells are shown along the plane at $X = 0$. The atoms (shown in yellow; not to scale) can be shared between different octants at such a plane.



The values 1.5 and 0.75 arise in Equation (6) from the fact that there are 12 faces and six half-axes that should contribute equally to each of the eight octants, so $\frac{12}{8}$ for

FIG. 6. The shared volumes of the planes and axes between the octants



Algorithm 4 Symmatrized

```

 $L_{cube} = L_{face} = L_{axis} = 0$ 
for  $X \leftarrow (D/2)$  to 1 do
  for  $Y \leftarrow (D/2)$  to 1 do
    for  $Z \leftarrow (D/2)$  to 1 do
       $L_{cube} += \frac{1}{(X^2+Y^2+Z^2)^{p/2}}$ 
       $L_{face} += \frac{1}{(X^2+Y^2)^{p/2}}$ 
       $L_{axis} += \frac{1}{X^p}$ 
return  $[L_{cube} + (1.5 \times L_{face}) + (0.75 \times L_{axis})] * 8$ 

```

the faces, and $\frac{6}{8}$ for the axes. The new serial algorithm, which automatically avoids the origin, can be written compactly as in Algorithm 4.

$$L_p = [L_{cube} + (1.5 * L_{face}) + (0.75 * L_{axis})] * 8 \quad (6)$$

To parallelize this, the basis is calculated as before, but the same basis does not hold for calculation of the face or axis (2- and 1-dimensional arrays, respectively). The calculation of those bases is shown in Algorithm 5. When looping through each volume (cube, face, or axis as shown in Algorithm 6), the values of (X_i, Y_i, Z_i) must be calculated relative to the appropriate basis for that volume (Equation 5 with $Basis$, $Basis_f$ or $Basis_a$, as needed). Note that the step sizes must be negative since the initial positions are set at points away from the origin. The new algorithm is computed by all threads as there is no need to find an origin thread.

Algorithm 5 Calculation of Basis

```

T = NumProcs
while ( $\sqrt{T}$  - Floor( $\sqrt{T}$ )) > 0 do
  | T --
Basisf = Floor( $\sqrt{T}$ )
Basisa = NumProcs - T

```

Algorithm 6 Parallelized & Symmatrized

```

Lcube = Lface = Laxis = 0
// Cube Volume
... calculate Xi, Yi, Zi relative to Basis ...
for X = Xi to X > 0 in steps of -Basis do
  | for Y = Yi to Y > 0 in steps of -Basis do
    | | for Z = Zi to Z > 0 in steps of -Basis do
      | | | Lcube +=  $\frac{1}{(X^2+Y^2+Z^2)^{p/2}}$ 
// Face & Axis
if Basisa > 0 then
  | if MyID < T then
    | ... calculate Xi, Yi relative to Basisf ...
    | for X = Xi to X > 0 in steps of -Basisf do
      | | for Y = Yi to Y > 0 in steps of -Basisf do
        | | | Lface +=  $\frac{1}{(X^2+Y^2)^{p/2}}$ 
    | else
      | ... calculate Xi relative to Basisa ...
      | for X = Xi to X > 0 in steps of -Basisa do
        | | Laxis +=  $\frac{1}{X^p}$ 
  | else
    | ... calculate Xi, Yi relative to Basisf ...
    | for X = Xi to X > 0 in steps of -Basisf do
      | | for Y = Yi to Y > 0 in steps of -Basisf do
        | | | Lface +=  $\frac{1}{(X^2+Y^2)^{p/2}}$ 
    | ... set Xi as ProcID + D ...
    | for X = Xi to X > 0 in steps of -NumProcs do
      | | Laxis +=  $\frac{1}{X^p}$ 
... MPI summation ...
return [Lcube + (1.5 × Lface) + (0.75 × Laxis)] * 8

```

4. Extending the Exploitation of Symmetry: BCC and FCC

For the BCC and FCC lattices, the same exploitation of octants can be used, but with special handling: The lattices must be thought of as an SC lattice with two and four basis atoms, respectively. The **for**-loop variables now indicate the coordinates of the new conventional unit cells, instead of just the atoms. The nearest-neighbor distance must be normalized properly to this new conventional unit cell (Table I), and the first triple-nested **for**-loop in Algorithm 7 can be computed similarly to the SC case, with the additional basis atom(s) added at each unit cell location. However, the face- and axis-cells are handled uniquely.

The multiple counts of basis atoms in Algorithm 7 are due to the way they are “shared” between the octants of the broken up cube. Along the face or axis, there

Algorithm 7 FCC - Symmatrized

```

Lcube = Lface = Laxis = 0
n = 2.0 // n = Normalization factor
// Basis atom offsets
b2x = 0.5; b2y = 0.5; b2z = 0.0
b3x = 0.0; b3y = 0.5; b3z = 0.5
b4x = 0.5; b4y = 0.0; b4z = 0.5
for X ← (D/2) to 1 do
  | for Y ← (D/2) to 1 do
    | | for Z ← (D/2) to 1 do
      | | | // First basis atom
      | | | R = (X2 + Y2 + Z2) * n
      | | | Lcube +=  $\frac{1}{R^{p/2}}$ 
      | | | // Second basis atom
      | | | R = ((X + b2x)2 + (Y + b2y)2 + (Z + b2z)2) * n
      | | | Lcube +=  $\frac{1}{R^{p/2}}$ 
      | | | ... similarly for the other basis atoms ...
      | | | R = (X2 + Y2) * n
      | | | Lface +=  $\frac{1}{R^{p/2}}$ 
      | | | ... then count basis atom 2 once ...
      | | | ... then count basis atoms 3 & 4 twice ...
      | | | R = (X2) * n
      | | | Laxis +=  $\frac{1}{R^{p/2}}$ 
      | | | ... then count basis atom 2 twice ...
      | | | ... then count basis atom 3 four times ...
      | | | ... then count basis atom 4 once ...
return [Lcube + (1.5 × Lface) + (0.75 × Laxis)] * 8


```

are cells where an atom sits astride the plane separating the octants. These atoms should only be counted once. However, there are other basis atoms in the volume of the unit cells immediate next to these planes (or around the axes) which need to be effectively counted once, but since the number of faces and axes that are shared is different from the number of octants, they need to be counted with special weights.

Consider the unit cells spanning the X-Y plane of a single octant. To minimize calculations, it is possible to compute only terms from these cells and use symmetry to apply the results to the Y-Z and X-Z planes. In the case of the SC lattice, all atoms sit astride the axes and faces evenly, so no special counting or weighing is needed. In the FCC case, two of the atoms sit evenly across the X-Y plane, and two are mirrored (Figure 7). These mirrored atoms must be counted twice as in Algorithm 7, and then the total contribution from the face can be added to the sum.

Similar to the faces, the algorithm need only compute the unit cells along a single half-axis. In the case of cells along the X-axis, the first basis atom is counted once as it is shared evenly between all four unit cells located around around the axis. The second and fourth basis atoms (locations described in Algorithm 7) are shared evenly between two cells, and mirrored across one plane, so they are each counted twice. The third basis atom is mirrored in all four unit cells along the axis, so it is counted four times.

FIG. 7. Conventional FCC unit cells along the X-Y plane (red). For face terms, the shared atoms (yellow spheres) are counted once in Algorithm 7, whereas the mirrored atoms (solid blue spheres) must be counted twice to make full use of symmetry. The faded blue spheres indicate which atoms are mirroring those indicated by the solid blue atoms. Gray spheres indicate other FCC atoms in other unit cells along the red plane.



In the BCC structure, the same mirroring principle applies: the second basis atom is counted once for cells in the 3-dimensional volume spanned, twice for cells along the face, and four times for cells along the axis.

Lattice	Basis Atoms	Normalization Factor
SC	1	1
BCC	2	$\frac{4}{3}$
FCC	4	2
DIA	12	$\frac{16}{3}$


TABLE I. Number of basis atoms and normalization factors in the conventional unit cells for each lattice.

5. Extending the Exploitation of Symmetry: DIA

For diamond, the conventional unit cell is essentially an FCC conventional cell with the addition of four more basis atoms within the volume of the cell at the tetrahedral positions. The algorithm requires further special handling due to the asymmetry of the tetrahedral positions across one axis. In the BCC and FCC cases, the symmetry between octants obeyed rotational symmetry


in that rotating the view 90 degrees about any axis resulted in viewing the exact same configuration of atoms. However, the diamond lattice does not have this symmetry. When rotating 90 degrees, the tetrahedral atoms now appear at different distances (Figure 8).

FIG. 8. Two conventional cells of the DIA lattice are shown. Distances to the tetrahedral atoms are not the same when rotating 90 degrees about any point. The blue spheres are the FCC-like basis atoms, and the red spheres indicate the tetrahedral atoms. The sizes of the spheres are not indicative of the sizes of the atoms at these sites.



Rather than settling for only four-fold speedup in symmetrization, one can fashion a new conventional unit cell that, while physically unrealistic, presents the same mathematical results as a real DIA lattice for this calculation. The new conventional unit cell has 12 basis atoms where four are the usual FCC-like atoms, four are the original tetrahedral atoms, and an additional four atoms occupy the location of where the tetrahedral atoms would appear to be if the viewer rotates 90 degrees (Figure 9).

FIG. 9. The 12-basis-atom conventional unit cell for calculations involving the diamond lattice. The orange spheres indicate the additional tetrahedral atoms.



All of the tetrahedral atom contributions to L_p now need to be counted for half of what they normally would

since there are now twice as many (Table II). Doing so yields an identical mathematical result from any other approach, but allows for full eight-fold speedup by only calculating one octant. The exact weights for each basis atom in each volume of the algorithm are described in Table II.

Basis Atom	Offset (X,Y,Z)	Cube Multiple	Face Multiple	Axis Multiple
1	(0, 0, 0)	1	1	1
2	($\frac{1}{2}$, $\frac{1}{2}$, 0)	1	1	2
3	(0, $\frac{1}{2}$, $\frac{1}{2}$)	1	2	4
4	($\frac{1}{2}$, 0, $\frac{1}{2}$)	1	2	2
5	($\frac{1}{4}$, $\frac{1}{4}$, $\frac{1}{4}$)	0.5	1	2
6	($\frac{3}{4}$, $\frac{3}{4}$, $\frac{1}{4}$)	0.5	1	2
7	($\frac{3}{4}$, $\frac{1}{4}$, $\frac{3}{4}$)	0.5	1	2
8	($\frac{1}{4}$, $\frac{3}{4}$, $\frac{1}{4}$)	0.5	1	2
9	($\frac{1}{4}$, $\frac{1}{4}$, $\frac{3}{4}$)	0.5	1	2
10	($\frac{3}{4}$, $\frac{3}{4}$, $\frac{3}{4}$)	0.5	1	2
11	($\frac{3}{4}$, $\frac{1}{4}$, $\frac{1}{4}$)	0.5	1	2
12	($\frac{1}{4}$, $\frac{3}{4}$, $\frac{1}{4}$)	0.5	1	2

TABLE II. Conventional DIA lattice basis atoms (2-8) and additional tetrahedral basis atoms (9-12) for use in Algorithms 4 and 6. The Cube Multiple represents the numerator used for the ($L_{cube/face/axis} +=$) lines in pseudocode.

6. Extending the Exploitation of Symmetry: HCP

For HCP, due to the hexagonal nature of the lattice, a completely different approach is used. Using the fact that the HCP lattice has alternating layers (ABABAB) and those layers have alternating and repeating rows, the structure can be logically constructed as four interpenetrating orthorhombic sub-lattices. One sub-lattice must be chosen to contain the (0,0,0) position, whereas the others are identical in shape but offset from this first sub-lattice (Figure 10). An algorithm can be constructed to calculate these four sub-lattices separately, and each can be parallelized as before.

The symmetry of this lattice can be easily broken down into quartets, but using octants will present a similar challenge as the DIA lattice. One of the four sub-lattices will extend slightly beyond what would be one of the faces between octants (Figure 11), and distances to each atom from the origin are not the same across this axis. The other three sub-lattices have atoms that either lie exactly on the faces, or completely within an octant. The solution, similar to DIA, is to double the number of atoms in the only sub-lattice with unevenly shared atoms. The positions of the extra atoms will be those that respect the rotational symmetry required for splitting the entire HCP lattice into equal octants. As with DIA, the algorithm halves the value added to L_p from each atom in this sub-lattice.

FIG. 10. The HCP lattice as composed of four (red, blue, green, orange) inter-penetrating orthorhombic lattices.





FIG. 11. Top-down view of the HCP lattice. The orange sub-lattice shown cuts unevenly across one of the yellow axes, where as the others either cut evenly or not at all.




7. Onionization

Running large, parallelized jobs on a cluster is convenient for solving large problems such as the algorithms described above. However, software and hardware errors do occasionally occur which can result in many lost CPU hours. As such, it is wise to break one large computation into many small ones. The result is a series of jobs that stack like layers of a (cubic) onion that are gradually added to the problem set (Figure 12, Left). This has the added benefit of being able to reduce roundoff error for extremely small terms (i.e. those layers at greatest distance) if one performs the sum of each job's return value from smallest to greatest.

In the symmatrized version of the program, the expedient use of this method would involve breaking the

FIG. 12. Left: Layers of computational ranges for different jobs shown stacking. The results are summed using the farthest first method. Right: Each layer can be split into six volumes: three volumes for the cubic space (blue), two volumes for the face (red), and one volume for the axis (green).



onion layer down into six new volumes: three volumes that span the main cube volume from the inner layer to the new outer layer, two regions to cover the face, and one region to cover the axis (Figure 12, Right). This avoids having to check that the coordinates covered are outside of the previous layer, and the cost of entering and leaving the **for**-loops is negligible compared to the number of **if**-statements avoided. Fortunately, the calculation of bases for each volume are identical to the non-onionized version.

III. RESULTS & APPLICATIONS

A. Lennard-Jones Lattice Constants

Using the symmatrized and parallelized algorithms described above, the Lennard-Jones lattice constants L_p have been calculated in the SC, BCC, FCC, HCP, and DIA lattices (Table IV). Terms with $p > 9$ are computed to 32 decimal digits, convenient for quadruple precision calculations. Those with $p \leq 9$ are computed to lower precision due to computational limits (Figure 2). In addition to extending the precision of these constants, there are corrections to terms with $p < 12$ previously published [10],[9]. The total speedup achieved going from the brute force method to the symmetric, parallel program was ~ 29 fold (Table III).

To validate these results, a Mathematica program similar to Algorithm 2 was used for several terms with $p \geq 12$ using infinite precision in all five lattices. Higher order terms were chosen because of the faster convergence of higher p values, and the comparative slowness of Algorithm 2 with the use of infinite precision. The results all agreed to the given precision in Table IV.

Moreover, a new method of computing any value that depends on distance between atoms in a crystal lattice has been created and optimized. This same algorithm can be tailored to look at other crystal energy functions, such as the Buckingham potential, SW potential, and

others.

Algorithm	Fraction of D^3 terms in L_p	Effective Speedup per CPU core
Simple (1)	1	1
Broken Down (2)	1	2.671
Parallel (3)	1	3.476
Symmetric Parallel (6)	0.1249	28.99

TABLE III. Speedup achieved for each algorithm in the SC lattice, as normalized to the calculation time of Algorithm 1. Results are similar for any distance-dependent calculation. Gains in Algorithm 2 are from avoiding the **if** statements. Likewise for Algorithm (3) but most threads are also able to avoid jumping into and out of **for** loops, which also avoids calculating some of the same components of the distance value. Algorithm 6 combines the advantages of parallelism and 8-fold symmetry for the greatest gains. All values of speedup are given per CPU core.

B. Other Classical Potentials

As the results in Table III are normalized to 1, similar speed-up values should be attainable for applications of this approach to other crystal calculations. For example, the SW potential is fit with as many as nine parameters:

$$U_{tot} = \epsilon \left[\sum_{i < j} f_2(r_{ij}/\sigma) + \sum_{\substack{i \neq j \\ j < k}} f_3(r_{ij}/\sigma, r_{ik}/\sigma, \theta_{ijk}) \right]$$

$$f_2(r) = \begin{cases} A (Br^{-p} - r^{-q}) \exp[(r-a)^{-1}], & r < a \\ 0, & r \geq a \end{cases}$$

$$f_3(r_{ij}, r_{ik}, \theta_{ijk}) = \lambda \left(\cos \theta_{ijk} + \frac{1}{3} \right)^2 \exp\left(\frac{\gamma}{r_{ij} - a}\right) \times \exp\left(\frac{\gamma}{r_{ik} - a}\right)$$

Fitting these parameters over many lattice sites and simulation requires lengthy computation, but it is also the case that the range of the potential is cut off at some arbitrary value (in this case, a). Indeed the cutoff is typically so short that only nearest- or next-to-nearest neighbors contribute to the total energy. Relaxing this parameter would allow simulation of more effects from vacancy or interstitial events. The algorithms described above can be used to compensate for the additional calculations, resulting in a potentially more transferable fit.

C. Applications to Crystal Defects

To simulate defects, one cannot use an algorithm for calculating over lattice sites in a perfect crystal. For example, to test or fit parameters for the creation energy

of a Frenkel pair [14], the atom at the origin in the algorithms in this paper can be instead walked along (or integrated over) the path of defect creation. A study is currently underway by the author to compare experimental data with recent parameterizations of the SW potential [7] and MD simulations of the threshold displacement energies for silicon [15]. This study relies on the algorithms presented in this paper to produce timely and accurate results.

In addition to point defects, plane defects can be simulated by displacing an entire algorithmic volume (as in Figures 3 or 12) for as many planes as desirable. This allows for a faster way to test the transferability of plane defects to other parameterizations of potentials. Either point or plane defects could be implemented as single occurrences, or uniform occurrences at regular intervals. Uniformly spread defects or point defects at the origin would still allow use of all the algorithms presented.

IV. CONCLUSIONS

A series of algorithms has been developed for fast calculation of any distant-dependent property of lattices, in-

cluding imperfect lattices. The algorithms are adaptable to simulate point or plane defects for fitting or testing transferability of parameters in classical potential formulas, and the speedup achieved allows for relaxation of cut-off parameters. These algorithms can be used in serial or parallel, with the greatest speedup achievable through parallelization. As an example of the power of the new algorithm, the Lennard-Jones lattice constants were determined up to 32 significant figures, extending their known precision, and in some cases correcting published figures.

V. ACKNOWLEDGMENTS

The author would like to express his sincere gratitude to his advisor, Jodi Cooley, for her continuous support of his studies. The author would like to thank Randy Scalise and John Fattaruso for the inspiration and assistance with this project. The author is grateful to the SMU Center for Scientific Computation and Amit Kumar for the incredible amount of support and CPU time that made this all possible. The author would also like to thank the SuperCDMS (Cryogenic Dark Matter Search) collaboration and its members for their feedback.

-
- [1] J. E. Jones and A. E. Ingham, Proceedings of the Royal Society of London A: Mathematical, Physical and Engineering Sciences **107**, 636 (1925).
- [2] R. A. Buckingham, Proceedings of the Royal Society of London A: Mathematical, Physical and Engineering Sciences **168**, 264 (1938).
- [3] F. H. Stillinger and T. A. Weber, Phys. Rev. B **31**, 5262 (1985).
- [4] Z. Jian, Z. Kaiming, and X. Xide, Phys. Rev. B **41**, 12915 (1990).
- [5] M. Timonova, B.-J. Lee, and B. J. Thijsse, Nuclear Instruments and Methods in Physics Research Section B: Beam Interactions with Materials and Atoms **255**, 195 (2007), computer Simulation of Radiation Effects in Solids.
- [6] R. Vink, G. Barkema, W. van der Weg, and N. Mousseau, Journal of Non-Crystalline Solids **282**, 248 (2001).
- [7] L. Pizzagalli, J. Godet, J. Gunol, S. Brochard, E. Holmstrom, K. Nordlund, and T. Albaret, Journal of Physics: Condensed Matter **25**, 055801 (2013).
- [8] W. Kahan, Commun. ACM **8**, 40 (1965).
- [9] P. Schwerdtfeger, N. Gaston, R. P. Krawczyk, R. Tonner, and G. E. Moyano, Phys. Rev. B **73**, 064112 (2006).
- [10] D. C. Wallace and J. L. Patrick, Phys. Rev. **137**, A152 (1965).
- [11] S. Balay, S. Abhyankar, M. F. Adams, J. Brown, P. Brune, K. Buschelman, L. Dalcin, V. Eijkhout, W. D. Gropp, D. Kaushik, M. G. Knepley, L. C. McInnes, K. Rupp, B. F. Smith, S. Zampini, H. Zhang, and H. Zhang, “PETSc Web page,” <http://www.mcs.anl.gov/petsc> (2016).
- [12] The IEEE-754 floating point standard defines quadruple-precision, 128-bit floats. These are implemented differently by various compilers as long-double, `_float128`, `PetscReal`, and others.
- [13] E. Lusk, N. Doss, and A. Skjellum, Parallel Computing **22**, 789 (1996).
- [14] J. Frenkel, Zeitschrift für Physik **35**, 652 (1926).
- [15] E. Holmström, A. Kuronen, and K. Nordlund, Phys. Rev. B **78**, 045202 (2008).

L_p	SC	BCC	FCC	HCP	DIA
L_4	16.53228	22.63872	25.33826	25.33908	10.23284
L_5	10.37752483	14.75850937	16.96751846	16.96843635	6.3127603582
L_6	8.40192397482754	12.2536678672923	14.4539210437445	14.4548972778416	5.11677158774719
L_7	7.4670577809188105309	11.054243479244464865	13.359387700742084043	13.360346776195552357	4.5944760255509476375
L_8	6.945807927226369624170778	10.35519790840251472712393	12.80193723137813255579318	12.80282185280989588716611	4.331913743971506684986912
L_9	6.6288591988867790990360972133	9.8945896563211153516496003879	12.492546702137558143156650385	12.493321725001781579567943092	4.1903721256503685465845227190
L_{10}	6.4261191025330890066321213261759	9.5644006153599478732928958387003	12.311245665477405791382158094686	12.311896233818981044642686360567	4.1110235994909590303207697180817
L_{11}	6.2922944992345673779692130757460	9.3132625373991001062237915286944	12.200920351277113166130939018073	12.201447099831954637516858217646	4.0654675989746082168420674657813
L_{12}	6.2021490450475185519304163922851	9.1141832680753588676564570885073	12.131880196544579708261946410532	12.132293769098917625885375250999	4.0389047128814160283254903749042
L_{13}	6.1405995800216921356289883683193	8.9518073185747151615181986692628	12.087726321352052662825461301813	12.088042550298439000808701615697	4.0232511870016901630637777123470
L_{14}	6.0981841257121521327529131655605	8.8167702284859198676408291902320	12.058991944350859312923039015626	12.059228255068241446619187406471	4.0139560884377807286889806009992
L_{15}	6.0687642950388921085943676325996	8.7029845599809255484889009743042	12.040024055099088629979906152137	12.040197144347223255169612620282	4.0084052364270646075922022605494
L_{16}	6.0482634695858416679464468171129	8.6062540475445294099631310987788	12.027354844018570329377774991884	12.027479419303856131335523169808	4.0050758707839297702973055370689
L_{17}	6.0339293163672074104867291112617	8.5235312504392982160783027553316	12.018809436710457796909425073283	12.018897719622859506995597162558	4.0030720422457274477625256930317
L_{18}	6.0238817078667147749258096087048	8.4525031686083817738457198340021	12.012998309665959588741240723167	12.013060023177408319000392309630	4.0018626537287036835660859738894
L_{19}	6.0168254563317377075012947930151	8.3913507914131177999359968485349	12.009019604439323572913310649568	12.009062224111209496811523499010	4.0011310801102128665086841693924
L_{20}	6.0118628308899457271005735996598	8.3386040056795629677517884205378	12.006280041326342657408789230664	12.006309158114658698075084825914	4.0006877092234562914662537575434
L_{21}	6.0083687575466831672374349304180	8.2930503704152943633396742334136	12.004384809362303299396537324646	12.004404510084773210744581189288	4.0004185815027828842036662413099
L_{22}	6.0059065261342911165963135002055	8.2536752180847796080069665089658	12.003068569322929886793306584316	12.003081784233296681711658420583	4.0002550042608394382922245458342
L_{23}	6.0041702400707480222133735785364	8.2196205348836491723537588485715	12.002151490974712110042308831699	12.002160286739322615229650383062	4.0001554703179378056666833678459
L_{24}	6.0029452081841294974019070764771	8.1901554754831630841615868276327	12.001510824939707072003031295877	12.001516638577045961535386165550	4.0000948484402457089307954562207
L_{25}	6.0020805203749133366722634113763	8.1646543519273306952128314265671	12.001062278709246141393049474196	12.001066097142027202635675470834	4.0000578966459919539177028099623
L_{26}	6.0014699724960860576163080284069	8.1425796159207988372706191903706	12.000747674897726915713658895972	12.000750168624485190911852889731	4.0000353574918921945136770397920
L_{27}	6.0010387522383048441317310970378	8.1234683158727891883161762963052	12.000526690212160028001079232466	12.000528310428505143624399658244	4.0000216015075983727843182332604
L_{28}	6.0007341210707894933633653237460	8.1069210710387173403772047642013	12.000371277553079701932705119123	12.000372325322411021726121333862	4.0000132018718538927954716341537
L_{29}	6.0005188792122114123860710817340	8.0925929383761217775918862369037	12.000261871447419639515536483048	12.000262546150133902013292069507	4.0000080707501767235974407653933
L_{30}	6.0003667748971840388354587433669	8.0801857499061731047494909917169	12.000184790059821196656550158876	12.000185222851788273771215661366	4.0000049351525392974917582258906
L_∞	6	8	12	12	4

TABLE IV. The Lennard-Jones lattice coefficients L_p in the SC, BCC, FCC, HCP, and DIA lattices